
BEL	Programmers' manual	IDENTIFICATION
<b>ATEQ</b>	F28Light Control	
AILG	DLL Version 2.004	Page 1/91

# **EVOLUTIONS**:


Date	Revision	Description
27/10/2015	F	Ethernet Interface for F28 light device.
05/11/2015	G	Update to 1.303 version, add VB.net samples.
12/11/2015	Н	Mistakes fix.
17/11/2015	1	Add Auto calibration functions
19/11/2015	J	Add parameters Option's (page 46) and auto calibration function (page 69).
24/11/2015	К	Add parameters and explanation, DLL version 1.402.
02/12/2015	L	Add explanation for auto-calibration with 5 devices, DLL version 1.402.
04/12/2015	М	Add "Start Auto Cal Offset for more than one head in VB.net" DLL version 1.402.
14/12/2015	N	Add specifics error codes (§ 3.9.1) add electronic regulator option, DLL version 1.500.
21/01/2016	0	Update error codes on §3.9.4 "Result status and alarms".
02/02/2016	Р	Update error codes on §3.9.4 "Result status and alarms".
15/02/2016	Q	Change to negatives values error codes on §3.9.4 "Result status and alarms".
25/07/2016	R	1- Use F28_RemoveModule then F28_AddModule without reinitialize all. 2- :FIX: Some declarations that can cause Unbalanced Stack
06/03/2017	S	Add F28 Jet Check special cycle, update error messages, dll version 2.004.

**Important!** This last DLL version works only with devices with firmware version  $\geq 1.500$ .



# Table of contents

1. INTRODUCTION	5
1.1. About this Document	5
1.2. What's needed for using the DLL	5
1.3. Application structure	5
1.4. Reminder of the ATEQ F28Light principle	5
1.5. F28 heads IP addresses	6
1.6. Switches configuration	6
1.7. IP address configuration	7
1.8. IP address loss	7
1.9. Data Definitions	7
2. STRUCTURE AND ENUMERATION	8
2.1. Enumeration	8
2.1.1. Type of test	
2.1.2. Pressure units	9
2.1.3. Leak units	10
2.1.4. Volume units	12
2.1.5. Fill mode	13
2.1.6. Boot/Application mode	14
2.1.7. Group Identifier	15
2.2. Module address	16
2.3. Step code	18
2.4. Identifier of module	18
2.5. Structure definitions in C/C++	19
2.6. Structure definitions in Visual Basic	21
2.7. Structure definitions in C#.Net	23
2.8. Function Return code	25
3. APPLICATION PROGRAMMING INTERFACE	26
3.1. Functional Groups in the API	26
3.2. Driver related functions	26
3.2.1. F28_Init	26
3.2.2. F28_OpenChannel	27
3.2.3. F28_Close	27
3.2.4. F28_GetDllMajorVersion	28
3.2.5. F28_GetDIIMinorVersion	28
3.3. Network related functions	29
3.3.1. F28_AddModule	29
3.3.2. F28_ReconnectModule	29
3.3.3. F28_RemoveModule	30
3.3.4. F28_RemoveAllModules	31



3.3.5. F28_ResetEthernetModule	31
3.4. Information related function	32
3.4.1. F28_RefreshModuleInformations	32
3.4.2. F28_GetSerialNumber	32
3.4.3. F28_GetModuleSoftVersion	33
3.4.4. F28_GetModuleHardVersion	34
3.4.5. F28_GetAddressIP	34
3.4.6. F28_ETHSoftVersion	35
3.4.7. F28_GetETHHardVersion	36
3.4.8. F28_GetSubnetMask	36
3.4.9. F28_GetGatewayAddressIP	37
3.4.10. F28_GetMACAddress	38
3.5. Unit Control related functions	39
3.5.1. F28_IsModuleConnected	39
3.5.2. F28_StartCycle	40
3.5.3. F28_StopCycle	40
3.6. Group Control related functions	41
3.6.1. F28_StartCycleByGroup	41
3.6.2. F28_StopCycleByGroup	41
3.7. Parameters related functions	42
3.7.1. Parameters structure F28_PARAMETERS	42
3.7.2. Options	46
3.7.3. F28_GetModuleParameters	47
3.7.4. F28_SetModuleParameters	48
3.8. Special cycle related functions	49
3.8.1. F28_StartAutoZeroPressure	49
3.8.2. F28_StartRegulatorAdjust	50
3.8.3. F28_StartLearningRegulator	51
3.8.4. F28_StartJetCheck	52
3.9. Result related functions	53
3.9.1. F28_ClearFIFOResults	53
3.9.2. F28_GetResultsCount	53
3.9.3. Result structure F28_RESULT	54
3.9.4. Result status and alarms	55
3.9.5. F28_GetNextResult	59
3.9.6. F28_GetLastResult	60
3.10. Real time cycle related functions	61
3.10.1. Real time data structure F28_REALTIME_CYCLE	61
3.10.2. F28_GetRealTimeData	62
3.11. Statistic counter related functions	63
3.11.1. Cycle statistic structure F28_CYCLE_STATISTICS	63



3.11.2. F28_GetCycleStatistics	64
3.11.3. Communication statistic structure F28_COMMUNICATION_STATISTICS	65
3.11.4. F28_GetCommunicationStatistics	66
3.12. Auto calibration functions	67
3.12.1. F28_GetEOCOffset	67
3.12.2. F28_GetEOCVolume	67
3.12.3. F28_StartAutoCalOffsetOnly	68
3.12.4. F28_StartAutoCalOffset (first step)	69
3.12.5. F28_StartAutoCalVolume (second step)	70
3.12.6. F28_StopAutoCal	71
3.12.7. F28_GetAutoCalAlarm	71
3.13. How to run calibration functions	72
3.13.1. Offset Calculation only	72
3.13.2. Volume and Offset Calculation	72
3.14. Calibration code example	73
3.14.1. Start calibration (first step)	73
3.14.2. Abort calibration	73
3.14.3. Continue calibration (second step)	74
3.14.4. Running calibration process	74
3.15. How to Run Calibration functions for 5 devices	76
3.15.1. We have 5 devices	76
3.15.2. Offset Calculation only	76
3.15.3. Volume & Offset Calculation	77
4. APPENDICIES 1	79
4.1. What's needed for using the samples project C++/MFC / C# / Vb.net	79
4.2. Visual C++/MFC sample	79
4.2.1. Build Project	79
4.3. Visual C# sample	81
4.3.1. Build Project	81
4.4. Visual Basic .net sample	83
4.4.1. Build Project	83
4.5. Sample code in VB.net	85
4.5.1. Get & Display Ethernet information	
4.5.2. Get module information	
4.5.3. Read real time status & Read Result cycle	88
4.5.4. Auto zero pressure	89
4.6. Start Auto Cal Offset for more than one head in VB.net	90

BEL	Programmers' manual	IDENTIFICATION
. ATEQ	F28Light Control	
	DLL Version 2.004	Page 5/91

### 1. INTRODUCTION

### 1.1. ABOUT THIS DOCUMENT

This manual describes the F28Light *Application Programming Interface* (*API*) and the containing functions. As a Win32 DLL for windows W7 & W8, it forms the interface between the user application and the F28Light.

### 1.2. WHAT'S NEEDED FOR USING THE DLL


vcredist\_x86.exe: Visual C++ Redistributable Packages for Visual Studio 2013.

**DLL Ethernet interface :** F28LightControl\_ETH.dll

The Visual C++ Redistributable Packages install run-time components that are required to run applications that are developed by using Visual Studio 2013, on computers that don't have Visual Studio 2013 installed.


These packages install run-time components of these libraries: C Runtime (CRT), Standard C++, ATL, MFC, C++ AMP, and OpenMP.

### 1.3. APPLICATION STRUCTURE



# 1.4. REMINDER OF THE ATEQ F28LIGHT PRINCIPLE

The ATEQ F28 Light is a compact air/air leak detector used to test the air-tightness of parts. The method used is based on the measurement of a small variation or drop in differential pressure between the **Test** and **Reference** parts, when both are filled to an identical pressure.




BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
•  <del>2111</del>	DLL Version 2.004	Page 6/91

# 1.5. F28 HEADS IP ADDRESSES



# 1.6. SWITCHES CONFIGURATION

On each head, on the main board, there's one switch to give a hardware address. The head must be configured as the following example.



BEL	Programmers' manual	IDENTIFICATION
. ATEQ	F28Light Control	
	DLL Version 2.004	Page 7/91

### 1.7. IP ADDRESS CONFIGURATION

The IP default configuration for the F28 Light device is in DHCP mode. This mode allows to automatically applying an IP address to the device by a rooter in the network.

For the first start, the device waits 10 seconds for a DHCP configuration. If it is not detected after these 10 seconds, the static **192.168.1.200** IP address is set.

To run the device in the network and update the boards, please use a static IP address.

This static IP address must be different for all the devices connected to the same network.

Keep one IP address for the PC and give different ones to the F28Light devices.

# Example:

**PC**: IP 192.168.1.1

> F28Light #1: IP 192.168.1.2

> F28Light #2: IP 192.168.1.3

> F28Light #3: IP 192.168.1.4

> F28Light #4: IP 192.168.1.5 Etc...


**Remind**: the network's rooter must have the same IP address root than the PC, example: **192.168.1**.X otherwise the device won't be detected.

### 1.8. IP ADDRESS LOSS

If the IP address is lost or nor recoverable, the communication between the device and the PC in the network is impossible.

To recover the communication, you must reset the IP address assignation, to be able to give another one.

For that, with the device powered off, set all the "Address" and the "Group" switches to 1.



Switches #1 to #8 (node) = On

Then power on the device for a few seconds and power off, the IP address is reseted.

### 1.9. DATA DEFINITIONS

Definition	Description
BYTE, UCHAR	Unsigned char (8 bits)
char	Signed char (8 bits)
short	Signed word (2 bytes)
WORD	Unsigned word (2 bytes)
float	Floating point single precision (4 bytes)
DWORD	Unsigned word (4 bytes)

BEL	Programmers' manual	IDENTIFICATION
. ATEQ	F28Light Control	
	DLL Version 2.004	Page 8/91

### 2. STRUCTURE AND ENUMERATION

### 2.1. ENUMERATION

# 2.1.1. Type of test

Test type parameter, to be use with "wTypeTest".

Definition	Value	Description
UNDEFINED_TEST	0	Not defined
LEAK_TEST	1	Leak test
SEALED_COMPONENT_TEST	2	Sealed components test
DESENSITIZED_MODE_TEST	3	Desensitized mode test for measurement of large leaks. *

# **Declaration in C/C++:**

```
enum F28_TYPE_TEST
     UNDEFINED_TEST,
     LEAK_TEST,
     SEALED_COMPONENT_TEST
     DESENSITIZED_MODE_TEST // Since v1.500 only
};
Visual Basic (Vb.Net):
Enum F28_TYPE_TEST
                      'Uses with wTypeTest parameter
     UNDEFINED_TEST
     LEAK_TEST
     SEALED_COMPONENT_TEST
     DESENSITIZED_MODE_TEST // Since v1.500 only
End Enum
C#.Net:
public enum F28_TYPE_TEST : byte
     UNDEFINED_TEST,
     LEAK_TEST,
     SEALED_COMPONENT_TEST
     DESENSITIZED_MODE_TEST // Since v1.500 only
};
```

\*Note: the desensitized mode is used for the measurement of large leaks, when the reject level required is above the full scale of the differential sensor; the measurement is performed by the pressure sensor.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
-	DLL Version 2.004	Page 9/91

### 2.1.2. Pressure units

Pressure unit parameter, to be use with "wPress1Unit".

Definition	Value	Description
PRESS_PA	0	Pascal
PRESS_KPA,	1	Kilo pascal
PRESS_MPA	2	Mega pascal
PRESS_BAR	3	Bar
PRESS_mBAR	4	Millibar
PRESS_PSI	5	PSI
PRESS_POINTS	6	Points

# Declaration in C/C++:

```
enum F28_PRESS_UNITS
{
         PRESS_PA,
         PRESS_KPA,
         PRESS_MPA,
         PRESS_BAR,
         PRESS_BAR,
         PRESS_PSI,
         PRESS_POINTS,
         NMAX_PRESS_UNITS
};
```

# Visual Basic (Vb.Net):

```
Enum F28_PRESS_UNITS As Byte
PRESS_PA
PRESS_KPA
PRESS_MPA
PRESS_BAR
PRESS_MBAR
PRESS_PSI
PRESS_POINTS
NMAX_PRESS_UNITS
End Enum
```

### C#.Net:

```
public enum F28_PRESS_UNITS : byte
{
     PRESS_PA,
     PRESS_KPA,
     PRESS_MPA,
     PRESS_BAR,
     PRESS_BBAR,
     PRESS_PSI,
     PRESS_POINTS,
     NMAX_PRESS_UNITS
};
```

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 2115	DLL Version 2.004	Page 10/91

# 2.1.3. Leak units

Leak unit parameter, to be use with "wLeakUnit".

Definition	Value	Description		
LEAK_PA	0	Pa		
LEAK_PASEC	1	Pa/s		
LEAK_PA_HR	2	Pa (High resolution)		
LEAK_PASEC_H	3	Pa/s(High resolution)		
LEAK_CAL_PA,	4	Calibrated Pascal.		
LEAK_CAL_PASEC,	5	Calibrated Pascal/second		
LEAK_CCMIN,	6	cm <sup>3</sup> /min		
LEAK_CCSEC,	7	cm <sup>3</sup> /s		
LEAK_CCH,	8	cm <sup>3</sup> /h.		
LEAK_MM3SEC,	9	mm³/s		
LEAK_CM3_SEC,	10	cm <sup>3</sup> /s		
LEAK_CM3_MIN,	11	cm <sup>3</sup> /mn		
LEAK_CM3_H,	12	cm <sup>3</sup> /h		
LEAK_ML_SEC,	13	ml/s		
LEAK_ML_MIN,	14	ml/min		
LEAK_ML_H,	15	ml/h		
		USA		
LEAK_INCH3_SEC,	16	Inch <sup>3</sup> /s		
LEAK_INCH3_MIN,	17	Inch <sup>3</sup> /mn		
LEAK_INCH3_H,	18	Inch <sup>3</sup> /h		
LEAK_FT3_SEC,	19	Feet <sup>3</sup> /s		
LEAK_FT3_MIN,	20	Feet <sup>3</sup> /mn		
LEAK_FT3_H,	21	Feet <sup>3</sup> /h		
LEAK_MMCE,	22	mmWg		
LEAK_MMCE_SEC,	23	mmWg/s		
LEAK_SCCM,	24	sccm		
LEAK_POINTS,	25	points		

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
-  <del>2111G</del>	DLL Version 2.004	Page 11/91

# **Declaration in C/C++:**

```
enum F28_LEAK_UNITS
     LEAK_PA,
     LEAK_PASEC,
     LEAK_PA_HR,
     LEAK_PASEC_HR,
     LEAK_CAL_PA,
     LEAK_CAL_PASEC,
     LEAK_CCMIN,
     LEAK_CCSEC,
     LEAK_CCH,
     LEAK_MM3SEC,
     LEAK_CM3_SEC,
     LEAK_CM3_MIN,
     LEAK_CM3_H,
     LEAK_ML_SEC,
     LEAK_ML_MIN,
     LEAK ML H,
     //USA-----
     LEAK_INCH3_SEC,
     LEAK_INCH3_MIN,
     LEAK_INCH3_H,
     LEAK_FT3_SEC,
     LEAK_FT3_MIN,
     LEAK_FT3_H,
     LEAK_MMCE,
     LEAK_MMCE_SEC,
     LEAK_SCCM,
     LEAK_POINTS,
     NMAX_LEAK_UNITS
```

# Visual Basic (Vb.Net):

```
Enum F28_LEAK_UNITS As Byte 'Uses with
               wLeakUnit parameter
     LEAK_PA
     LEAK_PASEC
     LEAK_PA_HR
     LEAK_PASEC_HR
     LEAK_CAL_PA
     LEAK_CAL_PASEC
     LEAK_CCMIN
     LEAK_CCSEC
     LEAK_CCH
     LEAK_MM3SEC
     LEAK_CM3_SEC
     LEAK_CM3_MIN
     LEAK_CM3_H
     LEAK_ML_SEC
     LEAK_ML_MIN
     LEAK_ML_H
     LEAK_INCH3_SEC
     LEAK_INCH3_MIN
     LEAK_INCH3_H
     LEAK_FT3_SEC
     LEAK_FT3_MIN
     LEAK_FT3_H
     LEAK MMCE
     LEAK_MMCE_SEC
     LEAK_SCCM
     LEAK_POINTS
     NMAX_LEAK_UNITS
End Enum
```

};

BEL	Programmers' manual	IDENTIFICATION
<b>ATEQ</b>	F28Light Control	
	DLL Version 2.004	Page 12/91

# C#.Net:

```
public enum F28_LEAK_UNITS : byte
     LEAK_PA,
     LEAK_PASEC,
     LEAK_PA_HR,
     LEAK_PASEC_HR,
     LEAK CAL PA,
     LEAK_CAL_PASEC,
     LEAK_CCMIN,
     LEAK_CCSEC,
     LEAK_CCH,
     LEAK_MM3SEC,
     LEAK_CM3_SEC,
     LEAK_CM3_MIN,
     LEAK_CM3_H,
     LEAK_ML_SEC,
     LEAK_ML_MIN,
     LEAK_ML_H,
     LEAK_INCH3_SEC,
     LEAK_INCH3_MIN,
     LEAK_INCH3_H,
     LEAK_FT3_SEC,
     LEAK_FT3_MIN,
     LEAK_FT3_H,
     LEAK_MMCE,
     LEAK_MMCE_SEC,
     LEAK_SCCM,
     LEAK_POINTS,
     NMAX_LEAK_UNITS
};
```

# 2.1.4. Volume units

Volume unit, to be use with "wVolumeUnit" parameter.

Definition	Value	Description
VOLUME_CM3	0	cm <sup>3</sup>
VOLUME_MM3	1	mm <sup>3</sup>
VOLUME_ML,	2	ml
VOLUME_LITRE	3	I
VOLUME_INCH3	4	inch <sup>3</sup>
VOLUME_FT3	5	Feet <sup>3</sup>

BEL	Programmers' manual	IDENTIFICATION
<b>ATEQ</b>	F28Light Control	
	DLL Version 2.004	Page 13/91

# **Declaration in C/C++:**

```
enum F28_ENUM_VOLUME_UNIT
{
     VOLUME_CM3,
     VOLUME_MM3,
     VOLUME_ML,
     VOLUME_LITRE,
     VOLUME_INCH3,
     VOLUME_FT3,
     NMAX_VOLUME_UNITS
};
Visual Basic (Vb.Net):
Enum F28_ENUM_VOLUME_UNIT As Byte 'Uses with wVolumeUnit parameter
     VOLUME CM3
     VOLUME_MM3
     VOLUME_ML
     VOLUME_LITRE
     VOLUME_INCH3
     VOLUME_FT3
     NMAX_VOLUME_UNITS
End Enum
C#.Net:
```

```
public enum F28_ENUM_VOLUME_UNIT : byte
{
     VOLUME_CM3,
     VOLUME_MM3,
     VOLUME_ML,
     VOLUME_LITRE,
     VOLUME_INCH3,
     VOLUME_FT3,
     NMAX_VOLUME_UNITS
};
```

### 2.1.5. Fill mode

Fill mode parameter, to be use with "wFillMode".

Definition	Value	Description	
STD_FILL_MODE	0	Standard fill mode	
AUTOFILL_MODE	1 Auto fill mode		
INSTRUCTION_MODE	Fill mode with instruction, only with the electrogram regulator option built-in (from v1.500)		
RAMP_MODE	3	Fill with a ramp, only with the electronic regulator option built-in (from v1.500)	

BEL	Programmers' manual	IDENTIFICATION
<b>ATEQ</b>	F28Light Control	
	DLL Version 2.004	Page 14/91

### **Declaration in C/C++:**

```
enum F28_ENUM_FILL_MODE
{
    STD_FILL_MODE,
    AUTOFILL_MODE,
    INSTRUCTION_MODE, // Electronic regulator option & from v1.500 only
    RAMP_MODE, // Electronic regulator option & from v1.500 only
    NMAX_FILL_MODE
};
```

# Visual Basic (Vb.Net):

```
Enum F28_ENUM_FILL_MODE As Byte
   STD_FILL_MODE
   AUTOFILL_MODE
   INSTRUCTION_MODE 'Electronic regulator option & from v1.500 only
   RAMP_MODE 'Electronic regulator option & from v1.500 only
   NMAX_FILL_MODE
```

# C#.Net:

End Enum

```
public enum F28_ENUM_FILL_MODE : byte
{
    STD_FILL_MODE,
    AUTOFILL_MODE,
    INSTRUCTION_MODE, // Electronic regulator option & from v1.500 only
    RAMP_MODE, // Electronic regulator option & from v1.500 only
    NMAX_FILL_MODE
};
```

# 2.1.6. Boot/Application mode

Returned by function "F28\_GetMode".

Declaration	Data type	Value	Description
F28_MODE_BOOT	short	1	Boot mode
F28_MODE_APPLICATION		2	Application mode

### **Declaration in C/C++:**

```
#define F28_MODE_BOOT 1
#define F28_MODE_APPLICATION 2
```

# Visual Basic (Vb.Net):

```
Enum F28_MODE As Byte
    F28_MODE_BOOT = 1
    F28_MODE_APPLICATION = 2
End Enum
```

## C#.Net:

```
public enum F28_MODE : byte
{
    F28_MODE_BOOT = 1,
    F28_MODE_APPLICATION = 2
};
```

BEL	Programmers' manual	IDENTIFICATION
<b>ATEQ</b>	F28Light Control	
•  <del>21114</del>	DLL Version 2.004	Page 15/91

# 2.1.7. Group Identifier

Value for variable "ucGroupID".

Variable	Data type	Value	Description
ucGroupID	ВҮТЕ	F28_GROUP_1 = 1, F28_GROUP_2 = 2, F28_GROUP_3 = 3, F28_GROUP_4 = 4, F28_GROUP_5 = 5, F28_GROUP_6 = 6, F28_GROUP_7 = 7, F28_GROUP_8 = 8, F28_GROUP_9 = 9, F28_GROUP_10 = 10,	Group identifier (1 -15)
		F28_GROUP_11 = 11, F28_GROUP_12 = 12, F28_GROUP_13 = 13, F28_GROUP_14 = 14, F28_GROUP_15 = 15	

### **Declaration in C/C++:**

```
enum
{
     F28\_GROUP\_1 = 1,
     F28_GROUP_2,
     F28_GROUP_3,
     F28_GROUP_4,
     F28_GROUP_5,
     F28_GROUP_6,
     F28_GROUP_7,
     F28_GROUP_8,
     F28_GROUP_9,
     F28_GROUP_10,
     F28_GROUP_11,
     F28_GROUP_12,
     F28_GROUP_13,
     F28_GROUP_14,
     F28_GROUP_15
};
```

# Visual Basic (Vb.Net):

```
Enum F28_GROUP_ID As Byte
     GROUP_1 = 1
     GROUP_2
     GROUP_3
     GROUP_4
     GROUP_5
     GROUP_6
     GROUP_7
     GROUP_8
     GROUP 9
     GROUP_10
     GROUP_11
     GROUP_12
     GROUP_13
     GROUP_14
     GROUP_15
     GROUP MAX
End Enum
```

BEL	Programmers' manual	IDENTIFICATION
. ATEQ	F28Light Control	
	DLL Version 2.004	Page 16/91

# C#.Net:

```
public enum F28_GROUP_ENUM : byte
     F28\_GROUP\_1 = 1,
     F28_GROUP_2,
     F28_GROUP_3,
     F28_GROUP_4,
     F28_GROUP_5,
     F28_GROUP_6,
     F28_GROUP_7,
     F28_GROUP_8,
     F28_GROUP_9,
     F28_GROUP_10,
     F28_GROUP_11,
     F28_GROUP_12,
     F28_GROUP_13,
     F28_GROUP_14,
     F28_GROUP_15
};
```

# 2.2. MODULE ADDRESS

Value for variable "ucModuleAddr".

Variable	Data type	Value	Description
ucModuleAddr	BYTE	F28_MODULE_ADDR_0 = 0	Station address (0 -15)
		F28_MODULE_ADDR_1 = 1	
		F28_MODULE_ADDR_2 = 2	
		F28_MODULE_ADDR_3 = 3	
		F28_MODULE_ADDR_4 = 4	
		F28_MODULE_ADDR_5 = 5	
		F28_MODULE_ADDR_6 = 6	
		F28_MODULE_ADDR_7 = 7	
		F28_MODULE_ADDR_8 = 8	
		F28_MODULE_ADDR_9 = 9	
		F28_MODULE_ADDR_10 = 10	
		F28_MODULE_ADDR_11 = 11	
		F28_MODULE_ADDR_12 = 12	
		F28_MODULE_ADDR_13 = 13	
		F28_MODULE_ADDR_14 = 14	
		F28_MODULE_ADDR_15 = 15	

BEL	Programmers' manual	IDENTIFICATION
. ATEQ	F28Light Control	
	DLL Version 2.004	Page 17/91

# **Declaration in C/C++:**

```
enum
{
     F28_MODULE_ADDR_0,
     F28 MODULE ADDR 1,
     F28_MODULE_ADDR_2,
     F28_MODULE_ADDR_3,
     F28_MODULE_ADDR_4,
     F28_MODULE_ADDR_5,
     F28_MODULE_ADDR_6,
     F28_MODULE_ADDR_7,
     F28 MODULE ADDR 8,
     F28_MODULE_ADDR_9,
     F28_MODULE_ADDR_10,
     F28_MODULE_ADDR_11,
     F28_MODULE_ADDR_12,
     F28_MODULE_ADDR_13,
     F28_MODULE_ADDR_14,
     F28 MODULE ADDR 15,
     F28_MAX_MODULES_BY_GROUP
```

# Visual Basic (Vb.Net):

```
Enum F28_MODULE_ADDR As Byte
     MODULE\_ADDR\_0 = 0
     MODULE_ADDR_1
     MODULE ADDR 2
     MODULE_ADDR_3
     MODULE_ADDR_4
     MODULE_ADDR_5
     MODULE_ADDR_6
     MODULE ADDR 7
     MODULE_ADDR_8
     MODULE ADDR 9
     MODULE_ADDR_10
     MODULE_ADDR_11
     MODULE ADDR 12
     MODULE_ADDR_13
     MODULE_ADDR_14
     MODULE_ADDR_15
     MODULE MAX
End Enum
```

### C#.Net:

};

```
public enum F28_MODULE_ADDR_ENUM : byte
     F28_MODULE_ADDR_0,
     F28_MODULE_ADDR_1,
     F28_MODULE_ADDR_2,
     F28_MODULE_ADDR_3,
     F28_MODULE_ADDR_4,
     F28_MODULE_ADDR_5,
     F28_MODULE_ADDR_6,
     F28_MODULE_ADDR_7,
     F28_MODULE_ADDR_8,
     F28_MODULE_ADDR_9,
     F28_MODULE_ADDR_10,
     F28_MODULE_ADDR_11,
     F28_MODULE_ADDR_12,
     F28 MODULE ADDR 13,
     F28 MODULE ADDR 14,
     F28_MODULE_ADDR_15,
     F28_MAX_MODULES_BY_GROUP
};
```

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 2115	DLL Version 2.004	Page 18/91

### 2.3. STEP CODE

Step code value for variable ucStatus inside F28\_REALTIME\_CYCLE structure.

Variable	Data type	Value	Description
ucStatus	BYTE	READY = 0,	Out of cycle
	BYTE	FILL_STEP = 1,	Fill step
	BYTE	STAB_STEP = 2,	Stabilization step
	BYTE	TEST_STEP = 3,	Test step
	BYTE	DUMP_STEP =4	Dump step

# enum F28\_ENUM\_STEP\_CODE { READY, FILL\_STEP, STAB\_STEP, TEST\_STEP, DUMP\_STEP

**Declaration in C/C++:** 

# Visual Basic (Vb.Net):

```
Enum F28_ENUM_STEP_CODE As Byte
READY
FILL_STEP
STAB_STEP
TEST_STEP
DUMP_STEP
End Enum
```

# C#.Net:

**}**;

```
public enum F28_ENUM_STEP_CODE : byte
{
    READY,
    FILL_STEP,
    STAB_STEP,
    TEST_STEP,
    DUMP_STEP
};
```

# 2.4. IDENTIFIER OF MODULE

Value for variable sModuleID. The identifier of the module is unique. It returns by the function "F28\_AddModule".

Variable	Data type	Description
sModuleID	short	High byte = index of channel.  Low byte = index of module.

BEL	Programmers' manual	IDENTIFICATION
. ATEQ	F28Light Control	
	DLL Version 2.004	Page 19/91

### 2.5. STRUCTURE DEFINITIONS IN C/C++

**Note**: All structures are 1 byte packed, for easy portability and data exchange between API and Visual basic 2013 application.

```
#pragma pack(push, 1 )
// Date structure
typedef struct
     WORD wYear;
     WORD wMonth;
     WORD wDay;
     WORD wHour;
     WORD wMinute;
     WORD wSecond;
} F28_DATE;
// Result structure
typedef struct
     UCHAR ucStatus;
     float fPressureValue;
     float fLeakValue;
     UCHAR ucUnitPressure;
     UCHAR ucUnitLeak;
     BYTE ucGroupID;
     BYTE ucModuleAddr;
     F28 DATE dateReceived;
}F28_RESULT;
// Real time structure
typedef struct F28_REALTIME_CYCLE
     UCHAR ucEndCycle;
     UCHAR ucStatus;
     float fPressureValue;
     float fLeakValue;
     UCHAR ucUnitPressure;
     UCHAR ucUnitLeak;
     float fInternalTemperature;
     float fPatm;
}F28_REALTIME_CYCLE;
// Cycle statistics structure
typedef struct
     DWORD dwTotalCycles;
     DWORD dwFailCycles;
     DWORD dwSuccessCycles;
}F28_CYCLE_STATISTICS;
```

BEL	Programmers' manual	IDENTIFICATION
_ATEQ	F28Light Control	
	DLL Version 2.004	Page 20/91

```
// Communication statistics structure
typedef struct
     DWORD dwTransmited;
     DWORD dwReceived;
     DWORD dwErrors;
}F28_COMMUNICATION_STATISTICS;
// Parameter structure
typedef struct F28 PARAMETERS
{
    WORD
           wTypeTest;
                             // STANDARD LEAK
    WORD
           wTpsFillVol;
    WORD
           wTpsTransfert;
    WORD wTpsFill;
    WORD wTpsStab;
          wTpsTest;
    WORD
    WORD
          wTpsDump;
    WORD
          wPress1Unit;
                             // See F28_PRESS_UNITS
    float fPress1Min;
    float fPress1Max;
    float fSetFillP1;
                             //instruction auto-fill mode
    float fRatioMax;
                             //LARGE LEAK mode only
    float fRatioMin;
                             //LARGE LEAK mode only
    WORD wFillMode;
                             //STD_FILL_MODE / AUTOFILL_MODE
    WORD
          wLeakUnit;
                             //See F28_LEAK_UNITS
    WORD
          wRejectCalc;
                             //Pa or Pa/s
    WORD
           wVolumeUnit;
                             //See F28_ENUM_VOLUME_UNIT
    float fVolume;
    float fRejectMin;
    float fRejectMax;
    float
           fCoeffAutoFill;
    WORD
           wOptions;
                             //Options parameters
    //V1.200
    float fPatmSTD;
                             //Patm standard condition (hPa)
                             //Temperature standard condition (in °C)
    float
           fTempSTD;
    float
           fFilterTime;
                             //in (s)
    //V1.300
                             //Offset on the leak
    float
           fOffsetLeak;
}F28_PARAMETERS;
#pragma pack(pop)
```

BEL	Programmers' manual	IDENTIFICATION
. ATEQ	F28Light Control	
	DLL Version 2.004	Page 21/91

# 2.6. STRUCTURE DEFINITIONS IN VISUAL BASIC

```
! ______
' Date structure
' ______
<StructLayout(LayoutKind.Sequential, Pack:=1)> _
Structure F28_DATE
    Dim wYear As UShort
    Dim wMonth As UShort
     Dim wDay As UShort
    Dim wHour As UShort
    Dim wMinute As UShort
     Dim wSecond As UShort
End Structure
! ______
' Result structure
' -----
<StructLayout(LayoutKind.Sequential, Pack:=1)>
Structure F28_RESULT
    Dim ucStatus As Byte
    Dim fPressureValue As Single
    Dim fLeakValue As Single
    Dim ucUnitPressure As Byte
    Dim ucUnitLeak As Byte
     Dim GroupID As Byte
                                       ' F28 GROUP ID
     Dim ModuleAddr As Byte
                                       ' F28_MODULE_ADDR
     Dim dateReceived As F28_DATE
End Structure
' real time result structure
' -----
<StructLayout(LayoutKind.Sequential, Pack:=1)> _
Structure F28 REALTIME CYCLE
     Dim ucEndCycle As Byte
     Dim ucStatus As Byte
     Dim fPressureValue As Single
    Dim fLeakValue As Single
    Dim ucUnitPressure As Byte
     Dim ucUnitLeak As Byte
     Dim fInternalTemperature As Single ' Temperature in °C
     Dim fPatm As Single
                                       ' Abs pressure in hPa
End Structure
' ______
' Statistic structure
! ______
<StructLayout(LayoutKind.Sequential, Pack:=1)> _
Structure F28_CYCLE_STATISTICS
     Dim dwTotalCycles As UInteger
     Dim dwFailCycles As UInteger
     Dim dwSuccessCycles As UInteger
End Structure
```

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 2115	DLL Version 2.004	Page 22/91

```
' Communication counter structure
' ______
<StructLayout(LayoutKind.Sequential, Pack:=1)> _
Structure F28_COMMUNICATION_STATISTICS
     Dim dwTransmited As UInteger
     Dim dwReceived As UInteger
     Dim dwErrors As UInteger
End Structure
' Parameter structure
<StructLayout(LayoutKind.Sequential, Pack:=1)> _
Structure F28_PARAMETERS
Dim wTypeTest As UShort ' STANDARD LEAK
     Dim wTpsFillVol As UShort
     Dim wTpsTransfert As UShort
     Dim wTpsFill As UShort
     Dim wTpsStab As UShort
     Dim wTpsTest As UShort
     Dim wTpsDump As UShort
     Dim wPress1Unit As UShort ' See F28_PRESS_UNITS
     Dim fPress1Min As Single
     Dim fPress1Max As Single
     Dim fSetFillP1 As Single' Setpoint auto-fill
     Dim fRatioMax As Single
     Dim fRatioMin As Single
     Dim wFillMode As UShort ' STD_FILL_MODE / AUTOFILL_MODE
     Dim wLeakUnit As UShort ' See F28_LEAK_UNITS
     Dim wRejectCalc As UShort ' Pa or Pa/s
     Dim wVolumeUnit As UShort ' See F28_ENUM_VOLUME_UNIT
     Dim fVolume As Single
     Dim fRejectMin As Single
     Dim fRejectMax As Single
     Dim fCoeffAutoFill As Single
     Dim wOptions As UShort ' Options parameters
     Dim fPatmSTD As Single ' Patm standard condition (hPa)
     Dim fTempSTD As Single ' Temperature standard condition (°C)
     Dim fFilterTime As Single ' in (s)
     Dim fOffsetLeak As Single' Offset on the leak
End Structure
```

BEL	Programmers' manual	IDENTIFICATION
. ATEQ	F28Light Control	
	DLL Version 2.004	Page 23/91

# 2.7. STRUCTURE DEFINITIONS IN C#.NET

```
[StructLayout(LayoutKind.Sequential, Pack = 1, CharSet = CharSet.Ansi)]
public struct F28_DATE
{
     public ushort usYear;
     public ushort usMonth;
     public ushort usDay;
     public ushort usHour;
     public ushort usMinute;
     public ushort usSecond;
};
[StructLayout(LayoutKind.Sequential, Pack = 1, CharSet = CharSet.Ansi)]
public struct F28_RESULT
{
     public byte
                     bStatus;
     public float
                     fPressureValue;
     public float
                     fLeakValue;
     public byte
                     bUnitPressure;
     public byte
                     bUnitLeak;
     public byte
                     bGroupID;
     public byte
                     bModuleAddr;
     public F28_DATE dateReceived;
};
[StructLayout(LayoutKind.Sequential, Pack = 1, CharSet = CharSet.Ansi)]
public struct F28_REALTIME_CYCLE
     public byte
                     bEndCycle;
     public byte
                     bStatus;
     public float
                     fPressureValue;
     public float
                     fLeakValue;
     public byte
                     bUnitPressure;
     public byte
                     bUnitLeak;
     public float
                     fInternalTemperature;
     public float
                     fPatm;
};
[StructLayout(LayoutKind.Sequential, Pack = 1, CharSet = CharSet.Ansi)]
public struct F28_CYCLE_STATISTICS
     public uint uiTotalCycles;
     public uint uiFailCycles;
     public uint uiSuccessCycles;
};
```

BEL	Programmers' manual	IDENTIFICATION
. ATEQ	F28Light Control	
	DLL Version 2.004	Page 24/91

```
[StructLayout(LayoutKind.Sequential, Pack = 1, CharSet = CharSet.Ansi)]
public struct F28_REGLAGE
     long
                 10ffset;
     float
                 fCoeffA;
                 fCoeffB;
     float
     F28_DATE
                 date;
     [MarshalAs(UnmanagedType.LPStr)] string Operator;
};
[StructLayout(LayoutKind.Sequential, Pack = 1, CharSet = CharSet.Ansi)]
public struct F28_COMMUNICATION_STATISTICS
     public uint uiTransmited;
     public uint uiReceived;
     public uint uiErrors;
};
[StructLayout(LayoutKind.Sequential, Pack = 1, CharSet = CharSet.Ansi)]
public struct F28_PARAMETERS
     public ushort usTypeTest;
                                   // STANDARD LEAK
     public ushort usTpsFillVol;
     public ushort usTpsTransfert;
     public ushort usTpsFill;
     public ushort usTpsStab;
     public ushort usTpsTest;
     public ushort usTpsDump;
     public ushort usPress1Unit;
                                   // See F28 PRESS UNITS
     public float fPress1Min;
     public float fPress1Max;
     public float fSetFillP1;
                                   //auto-fill mode instruction
     public float fRatioMax;
                                   //LARGE LEAK mode only
                                   //LARGE LEAK mode only
     public float fRatioMin;
     public ushort usFillMode;
                                   //STD_FILL_MODE / AUTOFILL_MODE
     public ushort usLeakUnit;
                                   //See F28_LEAK_UNITS
     public ushort usRejectCalc;
                                   //Pa or Pa/s
     public ushort usVolumeUnit;
                                   //See F28_ENUM_VOLUME_UNIT
     public float fVolume;
     public float fRejectMin;
     public float fRejectMax;
     public float fCoeffAutoFill;
                                   //Options parameters
     public ushort usOptions;
     public float fPatmSTD;
                                   //Patm standard condition (hPa)
     public float fTempSTD;
                                   //T° standard condition (in °C)
     public float fFilterTime;
                                   //in (s)
     public float fOffsetLeak;
                                   //Offset on the leak
};
```

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 2115	DLL Version 2.004	Page 25/91

# 2.8. FUNCTION RETURN CODE

Declaration	Data type	Value	Description
F28_FAIL	short	-1	Error
F28_OK		0	Ok

# Visual Basic (Vb.Net):

Declaration	Data type	Value	Description
F28_OFFLINE	short	0	Offline
F28_CONNECTED		1	Unit connected

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 2115	DLL Version 2.004	Page 26/91

### 3. APPLICATION PROGRAMMING INTERFACE

### 3.1. FUNCTIONAL GROUPS IN THE API

- Driver related functions
- Network related functions
- General device functions
- > Information related functions
- Unit Control related functions
- Group Control related functions
- > Parameters related functions
- Result related functions

### 3.2. DRIVER RELATED FUNCTIONS

# 3.2.1. F28\_Init

This function detects a head board and initializes a connection. It must be called first.

### **Function call:**

### C++:

short F28API F28\_Init(void);

# Visual Basic (Vb.Net):

Public Declare Function F28\_Init Lib "F28LightControl\_ETH.dll" () As Short

## C#.Net:

```
[DllImport("F28LightControl_ETH.dll")]
private static extern short F28_Init();
```

### **Arguments:**

	Argument	Data type	Description
r	none		

### **Return Value:**

**F28\_OK**: if the function succeeds.

**F28\_FAIL**: if the function fails.

BEL	Programmers' manual	IDENTIFICATION
<b>ATEQ</b>	F28Light Control	
.  <del>2111</del>	DLL Version 2.004	Page 27/91

# 3.2.2. F28\_OpenChannel

This function opens a channel.

### **Function call:**

### C++:

short F28API F28\_OpenChannel(void);

# Visual Basic (Vb.Net):

Public Declare Function F28\_OpenChannel Lib "F28LightControl\_ETH.dll" () \_ As Short

# C#.Net:

[DllImport("F28LightControl\_ETH.dll")]
private static extern short F28\_OpenChannel();

# **Arguments:**

Argument	Data type	Description
none		

### **Return Value:**

**F28\_OK**: if the function succeeds.

**F28\_FAIL**: if the function fails.

3.2.3. F28 Close

This function closes all channels.

### **Function call:**

### C++:

void F28API F28\_Close(void);

# Visual Basic (Vb.Net):

Public Declare Sub F28\_Close Lib "F28LightControl\_ETH.dll" ()

# C#.Net:

```
[DllImport("F28LightControl_ETH.dll")]
private static extern void F28_Close();
```

# **Arguments:**

Argument	Data type	Description
none		

# **Return Value:**

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 2115	DLL Version 2.004	Page 28/91

# 3.2.4. F28\_GetDIIMajorVersion

Read a major's version of the API.

### **Function call:**

### C++:

unsigned short F28API F28\_GetDllMajorVersion(void);

# Visual Basic (Vb.Net):

### C#.Net:

[DllImport("F28LightControl\_ETH.dll")]
private static extern ushort F28\_GetDllMajorVersion();

# **Arguments:**

Argument	Data type	Description
None		

Return Value: unsigned short

Major version

# 3.2.5. F28\_GetDIIMinorVersion

Read a minor's version of the API.

# **Function call:**

### C++:

unsigned short F28\_GetDllMinorVersion()

# Visual Basic (Vb.Net):

### C#.Net:

[DllImport("F28LightControl\_ETH.dll")]
private static extern ushort F28\_GetDllMinorVersion();

### **Arguments:**

Argument	Data type	Description
none		

Return Value: unsigned short

Minor version

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.   21.15	DLL Version 2.004	Page 29/91

### 3.3. NETWORK RELATED FUNCTIONS

# 3.3.1. F28 AddModule

Add F28 unit to the network.

### **Function call:**

### C++:

# Visual Basic (Vb.Net):

Public Declare Function F28\_AddModule Lib "F28LightControl\_ETH.dll" (ByVal ulIP As UInteger, ByVal ucModuleAddr As Byte, ByVal ucGroupID As Byte, ucTimeout As Byte) As Short

### C#.Net:

## **Arguments:**

Argument	Data type	Description
ullP	ULONG	IP address in long format
ucModuleAddr	BYTE	Module address
ucGroupID	BYTE	Group ID
ucTimeout	BYTE	Timeout in seconds

Return Value: short.

**F28 FAIL**: if the function fails.

**sModuleID**: High byte = channel's index, Low byte = module's index

# 3.3.2. F28 ReconnectModule

Reconnect F28 unit specified by module ID in the network.

### **Function call:**

### C++:

short F28API F28\_ReconnectModule(short sModuleID);

### Visual Basic (Vb.Net):

Public Declare Function F28\_ReconnectModule Lib "F28LightControl\_ETH.dll" \_ (ByVal sModuleID As Short) As Short

### C#.Net:

```
[DllImport("F28LightControl_ETH.dll")]
private static extern short F28_ReconnectModule(short sModuleID);
```

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
- <del> </del>	DLL Version 2.004	Page 30/91

# **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module

Return Value: short

**F28\_OK**: if the function succeeds.

F28\_FAIL: if the function fails.

# 3.3.3. F28\_RemoveModule

Remove F28 unit specified by module ID from network.

### **Function call:**

### C++:

short F28API F28\_RemoveModule(short sModuleID);

# Visual Basic (Vb.Net):

Public Declare Function F28\_RemoveModule Lib "F28LightControl\_ETH.dll" \_ (ByVal sModuleID As Short) As Short

## C#.Net:

[DllImport("F28LightControl\_ETH.dll")]
private static extern short F28\_RemoveModule(short sModuleID);

# **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module

Return Value: short

**F28\_OK**: if the function succeeds.

**F28\_FAIL**: if the function fails.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.   27.1.5	DLL Version 2.004	Page 31/91

# 3.3.4. F28\_RemoveAllModules

Remove all units specified by channel's ID from the network.

### **Function call:**

### C++:

short F28API F28 RemoveAllModules(BYTE ucChannelID);

# Visual Basic (Vb.Net):

Public Declare Function F28\_RemoveAllModules Lib "F28LightControl\_ETH.dll" \_ (ByVal ucChannelID As Byte) As Short

### C#.Net:

```
[DllImport("F28LightControl_ETH.dll")]
private static extern short F28_RemoveAllModules();
```

# **Arguments:**

Argument	Data type	Description
ucChannelID	BYTE	Channel identifier

Return Value: short

**F28\_OK**: if the function succeeds.

**F28\_FAIL**: if the function fails.

# 3.3.5. F28 ResetEthernetModule

To reset the Ethernet board, this is to fix a communication issue.

### **Function call:**

### C++:

short F28API F28\_ResetEthernetModule(short sModuleID); (

# Visual Basic (Vb.Net):

```
Public Declare Function F28_ResetEthernetModule Lib _ "F28LightControl_ETH.dll" _ (ByVal sModuleID As Short) As Short
```

# C#.Net:

```
[DllImport("F28LightControl_ETH.dll")]
private static extern short F28_ResetEthernetModule(short sModuleID);
```

# **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module

Return Value: short

**F28\_OK**: if the function succeeds.

**F28\_FAIL**: if the function fails.

BEL	Programmers' manual	IDENTIFICATION
<b>ATEQ</b>	F28Light Control	
	DLL Version 2.004	Page 32/91

### 3.4. Information related function

# 3.4.1. F28 RefreshModuleInformations

Query information about the module.

### **Function call:**

### C++:

short F28API F28\_RefreshModuleInformations(short sModuleID);

## Visual Basic (Vb.Net):

Public Declare Function F28\_RefreshModuleInformations Lib \_ "F28LightControl\_ETH.dll" (ByVal sModuleID As Short) As Short

### C#.Net:

[DllImport("F28LightControl\_ETH.dll")] private static extern short F28\_RefreshModuleInformations(short sModuleID);

## **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module

Return Value: short

**F28\_OK**: if the function succeeds. **F28\_FAIL**: if the function fails.

**Note**: this function must be called before F28\_GetSerialNumber, F28\_GetModuleSoftVersion, F28 GetModuleHardVersion.

# 3.4.2. F28 GetSerialNumber

Retrieve the current serial number from Module Information.

### **Function call:**

# C++:

### Visual Basic (Vb.Net):

Public Declare Function F28\_GetSerialNumber Lib "F28LightControl\_ETH.dll" \_ (ByVal sModuleID As Short, ByVal szSerialNumber As String, \_ ByVal Length As UShort) As Short

# C#.Net:

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 2115	DLL Version 2.004	Page 33/91

# **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module
szSerialNumber	array of char	Returned serial number
wLength	unsigned short	Length of char to read (20 chars max)

Return Value: short

**F28\_OK**: if the function succeeds. **F28\_FAIL**: if the function fails.

# 3.4.3. F28\_GetModuleSoftVersion

Retrieve the version of unit's firmware from Module Information.

### **Function call:**

### C++:

# Visual Basic (Vb.Net):

### C#.Net:

# **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module
szVersion	array of char	Returned software's version of the F28
wLength	unsigned short	Length of char to read

Return Value: short

**F28\_OK**: if the function succeeds.

**F28\_FAIL**: if the function fails.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 4114	DLL Version 2.004	Page 34/91

# 3.4.4. F28\_GetModuleHardVersion

Retrieve the board's hardware version from Module Information.

# **Function call:**

### C++:

# Visual Basic (Vb.Net):

### C#.Net:

# **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module
szVersion	array of char	Returned hardware's version of the F28
wLength	unsigned short	Lenght of byte to read

# Return Value: short

**F28\_OK**: if the function succeeds. **F28\_FAIL**: if the function fails.

# 3.4.5. F28\_GetAddressIP

Read the IP address of the Module in long format.

### **Function call:**

### C++:

short F28API F28\_GetAddressIP(short sModuleID, ULONG\* pAddressIP);

# Visual Basic (Vb.Net):

Public Declare Function F28\_GetAddressIP Lib "F28LightControl\_ETH.dll" (ByVal sModuleID As Short, ByRef pAddressIP As UInteger) As Short

### C#.Net:

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. AIL	DLL Version 2.004	Page 35/91

# **Arguments:**

Argument	Data type	Description
sModuleID	short	ID of module
pAddressIP	ULONG	Returned IP address of the module

Return Value: short

**F28\_OK**: if the function succeeds.

**F28\_FAIL**: if the function fails.

# 3.4.6. F28\_ETHSoftVersion

Read the version of Ethernet board firmware of the Module.

## **Function call:**

# C++:

# Visual Basic (Vb.Net):

```
Public Declare Function F28_GetETHSoftVersion Lib _ "F28LightControl_ETH.dll" (ByVal sModuleID As Short, _ ByVal szVersion As String, ByVal wLength As Short) As Short
```

# C#.Net:

# **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module
szVersion	array of char	Returned software's version of the Ethernet board
wLength	unsigned short	Length of char to read

Return Value: short

**F28\_OK**: if the function succeeds.

**F28 FAIL**: if the function fails.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.   21.15	DLL Version 2.004	Page 36/91

# 3.4.7. F28\_GetETHHardVersion

Read the hard version of Ethernet board of the Module.

### **Function call:**

### C++:

# Visual Basic (Vb.Net):

Public Declare Function F28\_GetETHHardVersion Lib \_

"F28LightControl\_ETH.dll" (ByVal sModuleID As Short, \_

ByVal szVersion As String, ByVal wLength As Short) As Short

### C#.Net:

# **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module
szVersion	array of char	Returned hardware's version of the Ethernet board
wLength	unsigned short	Length of char to read

# Return Value: short

**F28\_OK**: if the function succeeds.

**F28\_FAIL**: if the function fails.

# 3.4.8. F28 GetSubnetMask

Read the Subnet mask of the Module in long format.

### **Function call:**

### C++:

short F28API F28\_GetSubnetMask(short sModuleID, ULONG\* pAddressIP);

# Visual Basic (Vb.Net):

Public Declare Function F28\_GetSubnetMask Lib "F28LightControl\_ETH.dll" (ByVal sModuleID As Short, ByRef pAddressIP As UInteger) As Short

### C#.Net:

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.   27.1.5	DLL Version 2.004	Page 37/91

## **Arguments:**

Argument	Data type	Description
sModuleID	short	ID of module
pAddressIP	ULONG	Returned Subnet mask of the module

Return Value: short

**F28\_OK**: if the function succeeds.

**F28\_FAIL**: if the function fails.

# 3.4.9. F28\_GetGatewayAddressIP

Read the Gateway of the Module in long format.

#### **Function call:**

#### C++:

short F28API F28\_GetGatewayAddressIP(short sModuleID, ULONG\* pAddressIP);

## Visual Basic (Vb.Net):

Public Declare Function F28\_GetGatewayAddressIP Lib "F28LightControl\_ETH.dll" (ByVal sModuleID As Short, ByRef pAddressIP As UInteger) As Short

#### C#.Net:

#### **Arguments:**

Argument	Data type	Description
sModuleID	short	ID of module
pAddressIP	ULONG	Returned Gateway address of the module in long format

Return Value: short

**F28\_OK**: if the function succeeds.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 21125	DLL Version 2.004	Page 38/91

# 3.4.10. F28\_GetMACAddress

Read the MAC address of the Module Information.

#### **Function call:**

#### C++:

## Visual Basic (Vb.Net):

Public Declare Function F28\_GetMACAddress Lib "F28LightControl\_ETH.dll" \_ (ByVal sModuleID As Short, ByVal szMAC As String, ByVal \_ wLength As Short) As Short

#### C#.Net:

# **Arguments:**

Argument	Data type	Description
sModuleID	short	ID of module
szMAC	LPSTR	Returned MAC address of the module in string

Return Value: short

**F28\_OK**: if the function succeeds.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 21115	DLL Version 2.004	Page 39/91

# 3.5. Unit Control related functions

# 3.5.1. F28\_IsModuleConnected

Check if the module is connected.

#### **Function call:**

#### C++:

short F28API F28\_IsModuleConnected(short sModuleID);

# Visual Basic (Vb.Net):

Public Declare Function F28\_IsModuleConnected Lib \_ "F28LightControl\_ETH.dll" (ByVal sModuleID As Short) As Short

#### C#.Net:

[DllImport("F28LightControl\_ETH.dll")]
private static extern short F28\_IsModuleConnected(short sModuleID);

## **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module

Return Value: short

**F28\_CONNECTED**: if the module is connected. **F28\_NOT\_CONNECTED**: if the module is not connected.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.   27.1.5	DLL Version 2.004	Page 40/91

# 3.5.2. F28\_StartCycle

The function starts the test cycle of the module.

#### **Function call:**

#### C++:

short F28API F28\_StartCycle(short sModuleID);

## Visual Basic (Vb.Net):

Public Declare Function F28\_StartCycle Lib "F28LightControl\_ETH.dll" \_ (ByVal sModuleID As Short) As Short

#### C#.Net:

[DllImport("F28LightControl\_ETH.dll")]
private static extern short F28\_StartCycle(short sModuleID);

# **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module

Return Value: short

**F28\_OK**: if the function succeeds.

**F28\_FAIL**: if the function fails.

# 3.5.3. F28\_StopCycle

The function aborts the test cycle of the module.

#### **Function call:**

#### C++:

short F28API F28\_StopCycle(short sModuleID);

## Visual Basic (Vb.Net):

Public Declare Function F28\_StopCycle Lib "F28LightControl\_ETH.dll" \_ (ByVal sModuleID As Short) As Short

# C#.Net:

[DllImport("F28LightControl\_ETH.dll")]
private static extern short F28\_StopCycle(short sModuleID);

## **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module

Return Value: short

**F28\_OK**: if the function succeeds.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.   21.15	DLL Version 2.004	Page 41/91

#### 3.6. GROUP CONTROL RELATED FUNCTIONS

# 3.6.1. F28\_StartCycleByGroup

The function starts the test cycle of all units cycle in the defined group.

#### **Function call:**

#### C++:

short F28API F28\_StartCycleByGroup(BYTE ucGroupID);

#### Visual Basic (Vb.Net):

Public Declare Function F28\_StartCycleByGroup Lib \_ "F28LightControl\_ETH.dll" (ByVal ucGroupID As Byte) As Short

#### C#.Net:

[DllImport("F28LightControl\_ETH.dll")]
private static extern short F28\_StartCycleByGroup(byte bGroupID);

#### **Arguments:**

Argument	Data type	Description
ucGroupID	BYTE	Identifier of the group

Return Value: short

**F28\_OK**: if the function succeeds.

F28 FAIL: if the function fails.

# 3.6.2. F28\_StopCycleByGroup

The function aborts the test cycle of all units cycle in the defined group.

#### **Function call:**

#### C++:

short F28API F28\_StopCycleByGroup(BYTE ucGroupID);

## Visual Basic (Vb.Net):

Public Declare Function F28\_StopCycleByGroup Lib "F28LightControl\_ETH.dll" \_ (ByVal ucGroupID As Byte) As Short

# C#.Net:

[DllImport("F28LightControl\_ETH.dll")]
private static extern short F28\_StopCycleByGroup(byte bGroupID);

## **Arguments:**

Argument	Data type	Description
ucGroupID	BYTE	Identifier of the group

Return Value: short

**F28\_OK**: if the function succeeds.

BEL	Programmers' manual	IDENTIFICATION
<b>ATEQ</b>	F28Light Control	
.  <del>2111</del>	DLL Version 2.004	Page 42/91

# 3.7. PARAMETERS RELATED FUNCTIONS

# 3.7.1. Parameters structure F28\_PARAMETERS

Element	Data type	Descr	ription	
wTypeTest	WORD	Test type parameter		
wTpsFillVol	WORD	Fill time for volume transfer in 0.01 sec (0 – 650 sec)		
wTpsTransfert	WORD	Transfer time in 0.01 sec (	0 – 650 sec)	
wTpsFill	WORD	Fill time in 0.01 sec (0 – 6	50 sec)	
wTpsStab	WORD	Stabilization time in 0.01 s	ec (0 – 650 sec)	
wTpsTest	WORD	Test time in 0.01 sec (0 –	650 sec)	
wTpsDump	WORD	Dump time in 0.01 sec (0 -	- 650 sec)	
wPress1Unit	WORD	Unit of pressure # 1		
fPress1Min	float	Minimum pressure # 1		
fPress1Max	float	Maximum pressure # 1		
fSetFillP1	float	Setpoint pressure # 1		
fRatioMax	float	Max reject value for ratio F	P <sub>start</sub> /P <sub>end</sub>	
fRatioMin	float	Min reject value for ratio P <sub>start</sub> /P <sub>end</sub>		
wFillMode	WORD	Fill mode		
wLeakUnit	WORD	Leak unit		
wRejectCalc	WORD	Pa or Pa/s		
wVolumeUnit	WORD	Volume unit		
fVolume	float	Volume value		
fRejectMin	float	Reject Reference side	See reminder at the	
fRejectMax	float	Reject <b>Test</b> side	beginning of this manual.	
fCoeffAutoFill	float	Reserved		
wOptions	WORD	See paragraph 3.7.1) Options ("wOptions' parameter).		
FPatmSTD	float	Patm standard condition (hPa)		
FTempSTD	float	Temperature standard condition (°C)		
FFilterTime	float	Filter time in sec		
fOffsetLeak	float	Offset on the leak		

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 2115	DLL Version 2.004	Page 43/91

## **Declaration in C/C++:**

```
typedef struct
    WORD
           wTypeTest;
                             //STANDARD LEAK
    WORD
           wTpsFillVol;
    WORD
           wTpsTransfert;
    WORD wTpsFill;
    WORD wTpsStab;
    WORD wTpsTest;
   WORD wTpsDump;
WORD wPress1115
          wPress1Unit;
                             //See F28_PRESS_UNITS
    float fPress1Min;
    float fPress1Max;
    float fSetFillP1;
                             //instruction auto-fill mode
    float fRatioMax;
                             //LARGE LEAK mode only
    float fRatioMin;
                             //LARGE LEAK mode only
    WORD wFillMode;
                             //STD FILL MODE / AUTOFILL MODE
    WORD wLeakUnit;
                             //See F28_LEAK_UNITS
    WORD
WORD
           wRejectCalc;
                             //Pa or Pa/s
          wVolumeUnit;
                             //See F28_ENUM_VOLUME_UNIT
    float fVolume;
    float fRejectMin;
    float fRejectMax;
    float fCoeffAutoFill;
    WORD
          wOptions;
                             //Options parameters
    float fPatmSTD;
                             //Patm standard condition (hPa)
    float fTempSTD;
                             //Temperature standard condition (°C)
    float
           fFilterTime;
                             //in (s)
    float
           fOffsetLeak;
                             //Offset on the leak
}F28 PARAMETERS;
```

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 2115	DLL Version 2.004	Page 44/91

## **Declaration in Visual Basic 2013:**

```
<StructLayout(LayoutKind.Sequential, Pack:=1)> _
Structure F28_PARAMETERS
     Dim wTypeTest As UShort
                                    'STANDARD LEAK
     Dim wTpsFillVol As UShort
     Dim wTpsTransfert As UShort
     Dim wTpsFill As UShort
     Dim wTpsStab As UShort
     Dim wTpsTest As UShort
     Dim wTpsDump As UShort
     Dim wPress1Unit As UShort
                                    'See F28_PRESS_UNITS
     Dim fPress1Min As Single
     Dim fPress1Max As Single
     Dim fSetFillP1 As Single
                                    'Setpoint auto-fill
     Dim fRatioMax As Single
     Dim fRatioMin As Single
     Dim wFillMode As UShort
                                    'STD FILL MODE / AUTOFILL MODE
     Dim wLeakUnit As UShort
                                    'See F28_LEAK_UNITS
     Dim wRejectCalc As UShort
                                    'Pa or Pa/s
     Dim wVolumeUnit As UShort
                                    'See F28_ENUM_VOLUME_UNIT
     Dim fVolume As Single
     Dim fRejectMin As Single
     Dim fRejectMax As Single
     Dim fCoeffAutoFill As Single
     Dim wOptions As UShort
                                    'Options parameters
     Dim fPatmSTD As Single
                                    'Patm standard condition (hPa)
     Dim fTempSTD As Single
                                    'Temperature standard condition (°C)
     Dim fFilterTime As Single
                                    'in (s)
     Dim fOffsetLeak As Single
                                    'Offset on the leak
End Structure
```

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
-	DLL Version 2.004	Page 45/91

#### **Declaration in C#.Net:**

```
[StructLayout(LayoutKind.Sequential, Pack = 1, CharSet = CharSet.Ansi)]
public struct F28_PARAMETERS
                                   // STANDARD LEAK
     public ushort usTypeTest;
     public ushort usTpsFillVol;
     public ushort usTpsTransfert;
     public ushort usTpsFill;
     public ushort usTpsStab;
     public ushort usTpsTest;
     public ushort usTpsDump;
     public ushort usPress1Unit; // See F28_PRESS_UNITS
     public float fPress1Min;
     public float fPress1Max;
     public float fSetFillP1;
                                   //auto-fill mode instruction
     public float fRatioMax;
                                   //LARGE LEAK mode only
     public float fRatioMin;
                                   //LARGE LEAK mode only
     public ushort usFillMode;
                                   //STD_FILL_MODE / AUTOFILL_MODE
     public ushort usLeakUnit;
                                   //See F28_LEAK_UNITS
     public ushort usRejectCalc;
                                   //Pa or Pa/s
     public ushort usVolumeUnit;
                                   //See F28_ENUM_VOLUME_UNIT
     public float fVolume;
     public float fRejectMin;
     public float fRejectMax;
     public float fCoeffAutoFill;
     public ushort usOptions;
                                   //Options parameters
     public float fPatmSTD;
                                   //Patm standard condition (hPa)
     public float fTempSTD;
                                   //T° standard condition (in °C)
     public float fFilterTime;
                                   //in (s)
     public float fOffsetLeak;
                                   //Offset on the leak
};
```

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.   27.1.5	DLL Version 2.004	Page 46/91

# **3.7.2. Options**

# Uses with "wOptions" parameter

Element	Data type	Value	Description
wOptions	UShort	BIT_SIGN (bit 0)	Sign option validation
		BIT_NO_NEGATIVE_VALUE (bit 1)	No negative value validation
		BIT (bit 2 reserved)	Reserved
		BIT (bit 3 reserved)	Reserved
		BIT_TEST_PRESSURE_CORR (bit 4)	Test pressure correction validation
		BIT_ELECTRONIC_REGULATOR (bit 5)	Electronic regulator option validation

Bit	15 to 6	5	4	3	2	1	0
Option	Reserved	Electronic regulator option	Pressure compensation	Reserved	Reserved	No Negative	Sign

#### **Declaration in C/C++:**

```
enum F28_OPTIONS
{
    BIT_SIGN = 0,
    BIT_NO_NEGATIVE_VALUE = 1,
    BIT = 2, // reserved
    BIT = 3, // reserved
    BIT_TEST_PRESSURE_CORR = 4
    BIT_ELECTRONIC_REGULATOR = 5
};
```

# C#.Net:

```
public enum F28_OPTIONS : UShort
{
    BIT_SIGN = 0,
    BIT_NO_NEGATIVE_VALUE = 1,
    BIT = 2, // reserved
    BIT = 3, // reserved
    BIT_TEST_PRESSURE_CORR = 4,
    BIT_ELECTRONIC_REGULATOR = 5
};
```

# Visual Basic (Vb.Net):

```
Enum F28_OPTIONS As UShort
    BIT_SIGN = 0
    BIT_NO_NEGATIVE_VALUE = 1
    BIT = 2 'reserved
    BIT = 3 'reserved
    BIT_TEST_PRESSURE_CORR = 4
    BIT_ELECTRONIC_REGULATOR = 5
End Enum
```

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.   21.15	DLL Version 2.004	Page 47/91

# 3.7.3. F28\_GetModuleParameters

The function reads parameters from the defined module.

When querying the parameters the above F28\_PARAMETERS structure is expected in the function call.

#### **Function call:**

#### C++:

## Visual Basic (Vb.Net):

```
Public Declare Function F28_GetModuleParameters Lib _ "F28LightControl_ETH.dll" (ByVal sModuleID As Short, _ ByRef Para As F28_PARAMETERS) As Short
```

#### C#.Net:

## **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module
pPara	F28_PARAMETERS*	Pointer to a F28_PARAMETERS structure, to place returned values in.

Return Value: short

**F28\_OK**: if the function succeeds.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.   21.15	DLL Version 2.004	Page 48/91

# 3.7.4. F28\_SetModuleParameters

The function writes parameters, F28\_PARAMETERS structure, to the defined module.

#### **Function call:**

#### C++:

short F28API F28\_SetModuleParameters(short sModuleID, F28\_PARAMETERS\* pPara);

## Visual Basic (Vb.Net):

```
Public Declare Function F28_SetModuleParameters Lib _ "F28LightControl_ETH.dll"_ (ByVal sModuleID As Short, _ ByRef Para As F28_PARAMETERS) As Short
```

#### C#.Net:

#### **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module
pPara	F28_PARAMETERS*	Pointer to a F28_ PARAMETERS structure to write

Return Value: short

**F28\_OK**: if the function succeeds.

**F28\_FAIL**: if the function fails.

**Note**: the parameters must be written to the F28 module at least once after power on.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 2115	DLL Version 2.004	Page 49/91

#### 3.8. SPECIAL CYCLE RELATED FUNCTIONS

# 3.8.1. F28\_StartAutoZeroPressure

The function starts an auto-zero pressure special cycle of the defined module.

#### **Function call:**

#### C++:

short F28API F28\_StartAutoZeroPressure(short sModuleID, float fDumpTime);

## Visual Basic (Vb.Net):

```
Public Declare Function F28_StartAutoZeroPressure Lib _ "F28LightControl_ETH.dll" (ByVal sModuleID As Short, ByVal _ fDumpTime As Single) As Short
```

#### C#.Net:

## **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module
fDumpTime	float	Dump time in seconds.

Return Value: short

**F28\_OK**: if the function succeeds.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.   21.15	DLL Version 2.004	Page 50/91

# 3.8.2. F28\_StartRegulatorAdjust

This function allows adjusting manually the regulator.

Note: When running, a "Reset cycle" must be called to exit the function.

#### **Function call:**

#### C++:

short F28API F28\_StartRegulatorAdjust(short sModuleID);

# Visual Basic (Vb.Net):

Public Declare Function F28\_StartRegulatorAdjust Lib \_ "F28LightControl\_ETH.dll" (ByVal sModuleID As Short) As Short

## C#.Net:

[DllImport("F28LightControl\_ETH.dll")]
private static extern short F28\_StartRegulatorAdjust(short sModuleID);

## **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module

Return Value: short

**F28\_OK**: if the function succeeds.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 2115	DLL Version 2.004	Page 51/91

# 3.8.3. F28\_StartLearningRegulator

The function starts an auto-zero for the pressure sensor and then starts an electronic regulator learning special cycle of the defined module.

This special cycle starts automatically at the module power on.

#### **Function call:**

#### C++:

short F28API F28\_StartLearningRegulator(short sModuleID, float fDumpTime);

## Visual Basic (Vb.Net):

```
Public Declare Function F28_ StartLearningRegulator Lib _ "F28LightControl_ETH.dll" (ByVal sModuleID As Short, ByVal _ fDumpTime As Single) As Short
```

#### C#.Net:

# **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module
fDumpTime	float	Dump time in seconds.

Return Value: short

**F28\_OK**: if the function succeeds.

**F28 FAIL**: if the function fails.

**Note**: the Dump time (fDumpTime parameter) is the pressure sensor auto-zero time, after this time, the regulator learning cycle begins.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.  <del>2111</del>	DLL Version 2.004	Page 52/91

# 3.8.4. F28\_StartJetCheck

The function start a Jet check special cycle of the defined module.

#### **Function call:**

#### C++:

short F28API F28\_StartJetCheck(short sModuleID);

## Visual Basic (Vb.net)

Public Declare Function F28\_StartJetCheck Lib \_ "F28LightControl\_Eth.dll" (ByVal sModuleID As Short) As Short

#### C#.Net

[dllImport("F28LightControl\_ETH.dll")]
private static extern short F28\_StartJetCheck(short sModuleID);

# **Argument:**

Argument	Data type	Description
sModuleID	short	Identifier of module

Return Value: short

**F28\_OK**: if the function succeeds.

F28\_FAIL: if the function fails.

**Warning!** When this special cycle has run, the leak unit value (wLeakUnit) in the results becomes 255 that is a millimeters unit (mm).

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.  <del>2111</del>	DLL Version 2.004	Page 53/91

#### 3.9. RESULT RELATED FUNCTIONS

# 3.9.1. F28\_ClearFIFOResults

This function clears the result inside the FIFO.

Note: the FIFO contains only one result.

**Function call:** 

C++:

short F28API F28\_ClearFIFOResults(short sModuleID);

#### Visual Basic (Vb.Net):

Public Declare Function F28\_ClearFIFOResults Lib "F28LightControl\_ETH.dll" \_ (ByVal sModuleID As Short) As Short

#### C#.Net:

```
[DllImport("F28LightControl_ETH.dll")]
private static extern short F28_ClearFIFOResults(short sModuleID);
```

# **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module

Return Value: short

**F28\_OK**: if the function succeeds.

**F28\_FAIL**: if the function fails.

## 3.9.2. F28 GetResultsCount

This function reads the number of results available in FIFO.

Note: when the result is available, the result count is equal to 1.

Function call:

C++:

WORD F28API F28\_GetResultsCount(short sModuleID);

# Visual Basic (Vb.Net):

Public Declare Function F28\_GetResultsCount Lib "F28LightControl\_ETH.dll" \_ (ByVal sModuleID As Short) As UShort

#### C#.Net:

```
[DllImport("F28LightControl_ETH.dll")]
private static extern ushort F28_GetResultsCount(short sModuleID);
```

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 2115	DLL Version 2.004	Page 54/91

# **Arguments:**

Argument	Data type	Description
sModuleID	Short	Identifier of module

**Return Value:** short **Number of results:** 0 / 1

Note: the FIFO contains only one result.

# 3.9.3. Result structure F28\_RESULT

Element	Data type	Description
ucStatus	UCHAR	Status of result
fPressureValue	float	Pressure value
fLeakValue	float	Leak value
ucUnitPressure	UCHAR	Pressure unit
ucUnitLeak	UCHAR	Leak unit
ucGroupID	UCHAR	Group identifier
ucModuleAddr	UCHAR	Module identifier
wYear	WORD	Year
wMonth	WORD	Month
wDay	WORD	Day
wHour	WORD	Hour
wMinute	WORD	Minute
wSecond	WORD	Second

See result status below.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.  <del>2111</del>	DLL Version 2.004	Page 55/91


# 3.9.4. Result status and alarms

Element	Data type	Code	Description		Leak result value*
sn:	٦	0	STATUS_GOOD_PART	Pass part	Value
ucStatus	UCHAR	1	STATUS_TEST_FAIL_PART	Test fail part. Not used (Reject level at 999)	Value
		2	STATUS_REF_FAIL_PART	Reference fail part	Value
		3	STATUS_ALARM_EEEE	Large leak on Test side, over full scale	Value
		4	STATUS_ALARM_MMMM	Large leak on Reference side, over full scale	Value
		5	STATUS_ALARM_PPPP	Pressure over the maximum pressure range (Tester error)	-399.99
		6	STATUS_ALARM_MPPP	Pressure below the minimum pressure range (Tester error)	-399.99
		7	STATUS_ALARM_OFFD_FUITE	Differential sensor auto-zero error (Tester error)	-399.99
		8	STATUS_ALARM_OFFD_PRESSION	Piezo sensor auto-zero error (Tester error)	-399.99
				Over maximum pressure (pressure too high)	-399.99
		9	STATUS_ALARM_PST	if "Sign" is checked (vacuum or indirect test)	Value
		10	Below minimum pressure (pressure too low)	•	Value
		10	STATUS_ALARM_MPST	if "Sign" is checked (vacuum or indirect test)	-399.99
		11	STATUS_ALARM_CS_VOLUME_PE TIT	Fail Sealed components volume too small (Tester error)	-399.99
		12	STATUS_ALARM_CS_VOLUME_ GRAND	Fail Sealed components volume too large (Tester error)	-399.99
		13	STATUS_ALARM_ERREUR_PRESS _ CALIBRATION	Calibration pressure error (Tester error)	-399.99
		14	STATUS_ALARM_ERREUR_LEAK_ CALIBRATION	Calibration leak error (Tester error)	-399.99
		15	STATUS_ALARM_ERREUR_LINE_ PRESS_CALIB	Calibration line pressure error (Tester error)	-399.99
		16	STATUS_ALARM_APPR_REG_ ELEC_ERROR	Electronic regulator learning fail	-399.99
		17	STATUS_ALARM_TEST_PART_ LARGE_LEAK	Large leak on Test side Alarm (no value)	+998.00

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.   21.15	DLL Version 2.004	Page 56/91

Element	Data type	Code value	Description		Leak result value*
		18	STATUS_ALARM_REF_SIDE_ LARGE_LEAK	Large leak on Reference side Alarm (no value)	-399.99
			STATUS_ALARM_P_TOO_LARGE_	Over maximum pressure (pressure too high). Case A1	-399.99
		19	FILL See diagrams below	If "Sign" is checked (vacuum or indirect test) and over max pressure. Case A2	+999.00
			STATUS_ALARM_P_TOO_LOW_	Pressure Below min pressure (pressure too low). Case B1	+999.00
		20	FILL See diagrams below	If "Sign" is checked (vacuum or indirect test) and below min pressure. CaseB2	-399.99
		21	STATUS_ALARM_JET_CHECK_FAIL	Jet Check out of limits (Jet air supply out of limits or Jet damaged).	-399.99
		22	STATUS_ALARM_JET_CHECK_PASS	Jet Check special cycle succeed	-399.99

\*The "Leak result value" is sent in the result frame, these specific values are only available from the 1.500 DLL version.



BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 2115	DLL Version 2.004	Page 57/91

#### **Declaration in C/C++:**

```
typedef struct
    WORD wYear;
    WORD wMonth;
    WORD wDay;
    WORD wHour;
    WORD wMinute;
    WORD wSecond;
}F28_DATE;
typedef struct
    UCHAR ucStatus;
    float fPressureValue;
    float fLeakValue;
    UCHAR ucUnitPressure;
    UCHAR ucUnitLeak;
    BYTE ucGroupID;
    BYTE ucModuleAddr;
    F28_DATE dateReceived;
}F28_RESULT;
```

#### **Declaration in Visual Basic 2013:**

```
<StructLayout(LayoutKind.Sequential, Pack:=1)> _
Structure F28_DATE
    Dim wYear As UShort
    Dim wMonth As UShort
    Dim wDay As UShort
    Dim wHour As UShort
    Dim wMinute As UShort
    Dim wSecond As UShort
End Structure
<StructLayout(LayoutKind.Sequential, Pack:=1)> _
Structure F28 RESULT
    Dim ucStatus As Byte
    Dim fPressureValue As Single
    Dim fLeakValue As Single
    Dim ucUnitPressure As Byte
    Dim ucUnitLeak As Byte
    Dim GroupID As Byte
                                   'F28_GROUP_ID
    Dim ModuleAddr As Byte
                                   'F28_MODULE_ADDR
    Dim dateReceived As F28_DATE
End Structure
```

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.  <del>21119</del>	DLL Version 2.004	Page 58/91

## **Declaration in C#.Net:**

```
[StructLayout(LayoutKind.Sequential, Pack = 1, CharSet = CharSet.Ansi)]
public struct F28_DATE
     public ushort usYear;
     public ushort usMonth;
     public ushort usDay;
     public ushort usHour;
     public ushort usMinute;
     public ushort usSecond;
};
[StructLayout(LayoutKind.Sequential, Pack = 1, CharSet = CharSet.Ansi)]
public struct F28_RESULT
{
     public byte
                     bStatus;
     public float
                     fPressureValue;
     public float
                    fLeakValue;
                   bUnitPressure;
     public byte
     public byte
                    bUnitLeak;
     public byte bGroupID;
public byte bModuleAddr;
     public F28_DATE dateReceived;
};
```

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 21125	DLL Version 2.004	Page 59/91

# 3.9.5. F28\_GetNextResult

This function retrieves one result from the FIFO. When querying the above **F28\_RESULT** structure is expected in the function call.

Note: after reading, the result count is equal to 0.

## **Function call:**

#### C++:

short F28API F28\_GetNextResult(short sModuleID, F28\_RESULT\* pResult);

# Visual Basic (Vb.Net):

Public Declare Function F28\_GetNextResult Lib "F28LightControl\_ETH.dll" \_ (ByVal sModuleID As Short, ByRef Result As F28\_RESULT) As Short

## C#.Net:

# **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module
pResult	F28_RESULT*	Pointer to a F28_RESULT structure, to place returned values in.

Return Value: short

**F28\_OK**: if the function succeeds.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 21115	DLL Version 2.004	Page 60/91

# 3.9.6. F28\_GetLastResult

This function retrieves the last cycle result. When querying the above **F28\_RESULT** structure is expected in the function call.

#### **Function call:**

#### C++:

short F28API F28\_GetLastResult(short sModuleID, F28\_RESULT\* pResult);

## Visual Basic (Vb.Net):

Public Declare Function F28\_GetLastResult Lib "F28LightControl\_ETH.dll" \_ (ByVal sModuleID As Short, ByRef Result As F28\_RESULT) As Short

#### C#.Net:

# **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module
pResult	F28_RESULT*	Pointer to a F28_RESULT structure, to place returned values in.

Return Value: short

**F28\_OK**: if the function succeeds.

**F28\_FAIL**: if the function fails.

Note: if the result is valid, this function can be called one or more times.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 2115	DLL Version 2.004	Page 61/91

# 3.10. REAL TIME CYCLE RELATED FUNCTIONS

## 3.10.1. Real time data structure F28\_REALTIME\_CYCLE

Element	Data type	Description
ucEndCycle	UCHAR	1 = End of cycle, 0 = Cycle in progress
ucStatus	UCHAR	see Step code
fPressureValue	float	Pressure value
fLeakValue	float	Leak value
ucUnitPressure	UCHAR	Pressure unit
ucUnitLeak	UCHAR	Leak unit
fInternalTemperature	float	Temperature in °C
fPatm	float	Abs pressure in hPa

#### **Declaration in C/C++:**

```
// Real time structure
typedef struct F28_REALTIME_CYCLE
{
     UCHAR ucEndCycle;
     UCHAR ucStatus;
     float fPressureValue;
     float fLeakValue;
     UCHAR ucUnitPressure;
     UCHAR ucUnitLeak;
     float fInternalTemperature;
     float fPatm;
}F28_REALTIME_CYCLE;
```

#### **Declaration in Visual Basic 2013:**

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 21125	DLL Version 2.004	Page 62/91

#### C#.Net:

```
[StructLayout(LayoutKind.Sequential, Pack = 1, CharSet = CharSet.Ansi)]
public struct F28_REALTIME_CYCLE
     public byte
                    bEndCycle;
     public byte
                    bStatus;
     public float fPressureValue;
     public float
                   fLeakValue;
     public byte
                   bUnitPressure;
                  bUnitLeak;
     public byte
     public float
                   fInternalTemperature;
     public float
                   fPatm;
};
```

# 3.10.2. F28\_GetRealTimeData

The function reads real time data from the defined module. When querying, the above F28\_REALTIME\_CYCLE structure is expected in the function call.

#### **Function call:**

#### C++:

## Visual Basic (Vb.Net):

```
Public Declare Function F28_GetRealTimeData Lib "F28LightControl_ETH.dll" _ (ByVal sModuleID As Short, ByRef Cycle As _ F28_REALTIME_CYCLE) As Short
```

#### C#.Net:

#### **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module
pCycle	F28_REALTIME_CYCLE*	Pointer to a F28_REALTIME_CYCLE structure, to place returned values in.

Return Value: short

**F28\_OK**: if the function succeeds. **F28\_FAIL**: if the function fails.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
- 21115	DLL Version 2.004	Page 63/91

# 3.11. STATISTIC COUNTER RELATED FUNCTIONS

# 3.11.1. Cycle statistic structure F28\_CYCLE\_STATISTICS

Element	Data type	Description
dwTotalCycles	DWORD	Cycle counter
dwFailCycles	DWORD	Fail counter
dwSuccessCycles	DWORD	Pass counter

#### **Declaration in C/C++:**

```
typedef struct
{
         DWORD dwTotalCycles;
         DWORD dwFailCycles;
         DWORD dwSuccessCycles;
}F28_CYCLE_STATISTICS;
```

## **Declaration in Visual Basic 2013:**

```
<StructLayout(LayoutKind.Sequential, Pack:=1)> _
Structure F28_CYCLE_STATISTICS
    Dim dwTotalCycles As UInteger
    Dim dwFailCycles As UInteger
    Dim dwSuccessCycles As UInteger
End Structure
```

#### **Declaration in C#.Net:**

```
[StructLayout(LayoutKind.Sequential, Pack = 1, CharSet = CharSet.Ansi)]
public struct F28_CYCLE_STATISTICS
{
    public uint uiTotalCycles;
    public uint uiFailCycles;
    public uint uiSuccessCycles;
};
```

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 21115	DLL Version 2.004	Page 64/91

# 3.11.2. F28\_GetCycleStatistics

This function allows reading the cycle statistics.

When querying the the above cycle statistic, F28\_CYCLE\_STATISTICS, structure is expected in the function call.

## **Function call:**

#### C++:

## Visual Basic (Vb.Net):

```
Public Declare Function F28_GetCycleStatistics Lib _ "F28LightControl_ETH.dll" (ByVal sModuleID As Short, ByRef _ Info As F28_CYCLE_STATISTICS) As Short
```

#### C#.Net:

## **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module
plnfo	F28_CYCLE_STATISTICS*	Pointer to a F28_CYCLE_STATISTICS structure, to place returned values in.

Return Value: short

**F28\_OK**: if the function succeeds.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 2113	DLL Version 2.004	Page 65/91

# 3.11.3. Communication statistic F28\_COMMUNICATION\_STATISTICS

structure

Element	Data type	Description
dwTransmited	DWORD	Transmit counter
dwReceived	DWORD	Receive counter
dwErrors	DWORD	Error counter

# **Declaration in C/C++:**

```
typedef struct
{
        DWORD dwTransmited;
        DWORD dwReceived;
        DWORD dwErrors;
}F28_COMMUNICATION_STATISTICS;
```

#### **Declaration in Visual Basic 2013:**

```
<StructLayout(LayoutKind.Sequential, Pack:=1)> _
Structure F28_COMMUNICATION_STATISTICS
    Dim dwTransmited As UInteger
    Dim dwReceived As UInteger
    Dim dwErrors As UInteger
End Structure
```

#### **Declaration in C#.Net:**

```
[StructLayout(LayoutKind.Sequential, Pack = 1, CharSet = CharSet.Ansi)]
public struct F28_CYCLE_STATISTICS
{
    public uint uiTotalCycles;
    public uint uiFailCycles;
    public uint uiSuccessCycles;
};
```

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.   21.15	DLL Version 2.004	Page 66/91

# 3.11.4. F28\_GetCommunicationStatistics

This function allows reading the communication statistics.

When querying the above communication statistic structure, F28\_COMMUNICATION\_STATISTICS, is expected in the function call.

#### **Function call:**

#### C++:

## Visual Basic (Vb.Net):

Public Declare Function F28\_GetCommunicationStatistics Lib \_ "F28LightControl\_ETH.dll" (ByVal sModuleID As Short, ByRef \_ Info As F28\_COMMUNICATION\_STATISTICS) As Short

#### C#.Net:

## **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module
pInfo	F28_COMMUNICATION_STATISTICS*	Pointer to a F28_COMMUNICATION_STATISTICS structure, to place returned values in.

Return Value: short

**F28\_OK**: if the function succeeds.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.   27.1.5	DLL Version 2.004	Page 67/91

#### 3.12. AUTO CALIBRATION FUNCTIONS

## 3.12.1. F28 GetEOCOffset

This function allows reading the end of cycle for the offset calculation.

#### **Function call:**

#### C++:

UCHAR F28API F28\_GetEOCOffset(short sModuleID);

#### Visual Basic (Vb.Net):

Public Declare Function F28\_GetEOCOffset Lib "F28LightControl\_ETH.dll"\_ (ByVal sModuleID As Short) As Byte

#### C#.Net:

[DllImport(strDllName)]
private static extern byte F28\_GetEOCOffset(short sModuleID);

## **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module

#### Return Value: short

**0**: Cycle in progress.

1: End of cycle.

# 3.12.2. F28\_GetEOCVolume

This function allows reading the end of cycle for the volume measurement.

#### **Function call:**

#### C++:

UCHAR F28API F28\_GetEOCVolume(short sModuleID);

# Visual Basic (Vb.Net):

Public Declare Function F28\_GetEOCVolume Lib "F28LightControl\_ETH.dll"\_ (ByVal sModuleID As Short) As Byte

# C#.Net:

[DllImport(strDllName)]

private static extern byte F28\_GetEOCVolume(short sModuleID); Coming soon.

## **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module

#### Return Value: short

**0**: Cycle in progress.

1: End of cycle.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.   21.15	DLL Version 2.004	Page 68/91

# 3.12.3. F28\_StartAutoCalOffsetOnly

This function allows calculating the offset of the measurement only.

#### **Function call:**

#### C++:

## Visual Basic (Vb.Net):

```
Public Declare Function F28_StartAutoCalOffsetOnly Lib _ "F28LightControl_ETH.dll" (ByVal sModuleID As Short, ByVal _ wNbCycles As UShort, ByVal wInterCycleTime As UShort, ByVal _ f0ffsetMax As Single) As Short
```

#### C#.Net:

## **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module
wNbCycles	WORD	Number of cycles of offset calculation
wInterCycleTime	WORD	Time between each offset cycle (ms)
fOffsetMax	float	Maximum reject for the calculated offset (sccm)

Return Value: short

**F28\_OK**: if the function succeeds.

**F28\_FAIL**: if the function fails.

**Important**! For complete calibration, the offset calibration must be carried on and succeed in first step and then the volume measurement succeed in second step.

BEL	Programmers' manual IDENTIFICATIO		
ATEQ	F28Light Control		
.   <del></del>	DLL Version 2.004	Page 69/91	

# 3.12.4. F28\_StartAutoCalOffset (first step)

This function allows calculating the offset of the measurement; it is the first step of volume and offset calculation.

#### **Function call:**

#### C++:

## Visual Basic (Vb.Net):

Public Declare Function F28\_StartAutoCalOffset Lib "F28LightControl\_ETH.dll"\_
(ByVal sModuleID As Short, ByVal wNbCycles As UShort, ByVal \_
wInterCycleTime As UShort, ByVal fOffsetMax As Single) As Short

#### C#.Net:

[DllImport(strDllName)]

## **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module
wNbCycles	WORD	Number of cycles of offset calculation
wInterCycleTime	WORD	Time between each offset cycle
fOffsetMax	float	Maximum reject for the calculated offset

Return Value: short

**F28\_OK**: if the function succeeds.

**F28\_FAIL**: if the function fails.

**Note**: if this function succeeds, the second step (volume measurement) is required to complete the calibration.

BEL	Programmers' manual IDENTIFICATIO		
ATEQ	F28Light Control		
.   2111 %	DLL Version 2.004	Page 70/91	

# 3.12.5. F28\_StartAutoCalVolume (second step)

This function allows measuring the volume of the installation; it is the second step of volume and offset calculation.

#### **Function call:**

#### C++:

## Visual Basic (Vb.Net):

Public Declare Function F28\_StartAutoCalVolume Lib "F28LightControl\_ETH.dll"\_
(ByVal sModuleID As Short, ByVal wNbCycles As UShort, ByVal \_
wInterCycleTime As UShort, ByVal fLeak As Single, ByVal \_
fPressure As Single, ByVal fVolMin As Single, ByVal fVolMax \_
As Single) As Short

#### C#.Net:

[DllImport(strDllName)]

#### **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module
wNbCycles	WORD	Number of cycles of offset calculation
wInterCycleTime	WORD	Time between each offset cycle (ms)
fLeak	float	Value of the master leak (sccm)
fPressure	float	Pressure value of the master leak (bar)
fVolMin	float	Maximum reject for the measured volume (cm <sup>3</sup> )
fVolMax	float	Minimum reject for the measured volume (cm <sup>3</sup> )

Return Value: short

**F28\_OK**: if the function succeeds.

**F28\_FAIL**: if the function fails.

**Note**: if this second function succeeds, the calibration is complete.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.   21.15	DLL Version 2.004	Page 71/91

# 3.12.6. F28\_StopAutoCal

This function allows aborting any auto calibration cycles. This function must be called to abort a current calibration process.

#### **Function call:**

#### C++:

short F28API F28\_StopAutoCal(short sModuleID);

## Visual Basic (Vb.Net):

Public Declare Function F28\_StopAutoCal Lib "F28LightControl\_ETH.dll" \_ (ByVal sModuleID As Short) As Short

#### C#.Net:

[DllImport(strDllName)]
private static extern short F28\_StopAutoCal(short sModuleID);

#### **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module

Return Value: short

**F28\_OK**: if the function succeeds.

**F28\_FAIL**: if the function fails.

## 3.12.7. F28\_GetAutoCalAlarm

This function allows reading the if an alarm has been triggered during the calibration cycles.

#### **Function call:**

#### C++:

UCHAR F28API F28\_GetAutoCalAlarm(short sModuleID);

#### Visual Basic (Vb.Net):

Public Declare Function F28\_GetAutoCalAlarm Lib "F28LightControl\_ETH.dll"\_ (ByVal sModuleID As Short) As Byte

## C#.Net:

[DllImport(strDllName)]
private static extern byte F28\_GetAutoCalAlarm(short sModuleID);

# **Arguments:**

Argument	Data type	Description
sModuleID	short	Identifier of module

Return Value: short

**= 0**: no Alarm.

**≠ 0**: Alarm triggered.

BEL	Programmers' manual	IDENTIFICATION
_ATEQ	F28Light Control	
	DLL Version 2.004	Page 72/91

#### 3.13. How to run calibration functions

## 3.13.1. Offset Calculation only

1) Start Offset calculation:

```
// Use: F28_StartAutoCalOffsetOnly(m_hDevice, m_wNbCycles, m_wInterCycle);
```

2) Wait End of Cycle of Offset calculation:

```
// Use: While (!F28_GetEOCOffset(m_hDevice))
```

3) Read Auto Calibration alarm:

```
// Use: F28_GetAutoCalAlarm( m_hDevice)
```

4) If no alarm, read and save parameters:

```
// Use: F28 GetParameters(m DeviceInfo.hHandle, &tPara) == F28 OK)
```

#### 3.13.2. Volume and Offset Calculation

1) State Offset calculation:

```
// Use: F28_StartAutoCalOffset(m_hDevice, m_wNbCycles, m_wInterCycle);
```

2) Wait End of Cycle of Offset calculation:

```
// Use: While (!F28_GetEOCOffset(m_hDevice))
```

3) Wait Master leak:

```
// Ask user to plug master leak
```

4) if (Wait master leak Ok) start volume calculation:

5) Wait End of Cycle of Volume calculation:

```
// Use: (!F28_GetEOCVolume(m_hDevice))
```

6) Read Auto Calibration alarm:

```
// Use: F28_GetAutoCalAlarm( m_hDevice)
```

7) If no alarm, read and save parameters:

```
// Use: F28_GetParameters((m_hDevice, &tPara) == F28_OK)
```

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.  <del>2111</del>	DLL Version 2.004	Page 73/91

#### 3.14. Calibration code example

## 3.14.1. Start calibration (first step)

```
***************
' Start Calibration
Public Function StartCal(sModuleID As Short, ucMode As Byte, _
wNbCycles As UShort, _
wInterCycle As UShort, _
fOffsetMax As Single,
Optional fVolumeLeak As Single = 0,
Optional fVolumePressure As Single = 0, _
Optional fVolumeMin As Single = 0,
Optional fVolumeMax As Single = 0) As Boolean
Dim bRet As Boolean
bRet = False
If sModuleID > 0 Then
      m_wNbCycles = wNbCycles
      m_wInterCycle = wInterCycle
      m_fOffsetMax = fOffsetMax
      m_fVolumeLeak = fVolumeLeak
      m_fVolumePressure = fVolumePressure
      m fVolumeMin = fVolumeMin
      m_fVolumeMax = fVolumeMax
      m_sModuleId = sModuleID
      m_ucMode = ucMode
      m \text{ wError} = 0
      m_ucPhase = CAL_AUTO_PHASES.AUTO_START_OFFSET ' CAL_AUTO_PHASES.AUTO_INIT
      m_bRunning = True
      bRet = True
End If
Return bRet
End Function
```

## 3.14.2. Abort calibration

BEL	Programmers' manual	IDENTIFICATION
<b>ATEQ</b>	F28Light Control	
. 21115	DLL Version 2.004	Page 74/91

## 3.14.3. Continue calibration (second step)

# 3.14.4. Running calibration process

```
' Purpose : Run Calibration
' Return :
' - True : EOC calibration
' - False : Running
Public Function RunCal() As Boolean
Dim sRet As Short
Dim bReturn As Boolean
' Not End of Run
bReturn = False
Select Case m_ucPhase
Case CAL_AUTO_PHASES.AUTO_START_OFFSET ' Start auto Cal
       If (m_ucMode = MODE_AUTO_CAL.OFFSET) Then
              sRet = F28_StartAutoCalOffsetOnly(m_sModuleId, m_wNbCycles, m_wInterCycle,
              m fOffsetMax)
              Else
              sRet = F28_StartAutoCalOffset(m_sModuleId, m_wNbCycles, m_wInterCycle,
              m_fOffsetMax)
       End If
       If (sRet = F28 RETURN.F28 OK) Then
              m ucPhase = CAL AUTO PHASES.AUTO WAIT EOC OFFSET
       Else
              m_wError = m_ucPhase
              m_ucPhase = CAL_AUTO_PHASES.AUTO_END
       End If
Case CAL_AUTO_PHASES.AUTO_WAIT_EOC_OFFSET ' Wait EOC Offset
       If (F28_GetEOCOffset(m_sModuleId) > 0) Then
              If (m_ucMode = MODE_AUTO_CAL.OFFSET) Then
                     m_wError = 0 ' Pas d'erreur
                     m_ucPhase = CAL_AUTO_PHASES.AUTO_END
                     m_wError = m_ucPhase
                     m_ucPhase = CAL_AUTO_PHASES.AUTO_WAIT_MASTER_LEAK
              End If
Case CAL_AUTO_PHASES.AUTO_WAIT_MASTER_LEAK ' Waiting master leak
        ' Wait validation from user
       ' Do nothing
Case CAL AUTO PHASES.AUTO START VOLUME ' Start auto volume
       If (F28_StartAutoCalVolume(m_sModuleId, _
              m_wNbCycles, _
              m_wInterCycle, _
              m fVolumeLeak, _
```

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.   27.1.5	DLL Version 2.004	Page 75/91

```
m_fVolumePressure, _
               m_fVolumeMin,
               m_fVolumeMax) = F28_RETURN.F28_OK) Then
               m_ucPhase = CAL_AUTO_PHASES.AUTO_WAIT_EOC_VOLUME
       Else
               m_wError = m_ucPhase
               m_ucPhase = CAL_AUTO_PHASES.AUTO_END
       End If
Case CAL_AUTO_PHASES.AUTO_WAIT_EOC_VOLUME ' Wait EOC Auto volume
       If (F28_GetEOCVolume(m_sModuleId) > 0) Then
               m wError = 0 ' Pas d'erreur
               m_ucPhase = CAL_AUTO_PHASES.AUTO_END
       End If
Case CAL_AUTO_PHASES.AUTO_END ' End of auto calibration
       m_wError = m_ucPhase
m_ucPhase = CAL_AUTO_PHASES.AUTO_IDDLE
       m_bRunning = False
       bReturn = True
Case CAL_AUTO_PHASES.AUTO_IDDLE ' Ready do nothing ' do nothing
End Select
Return bReturn
End Function
```

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.  <del>2111</del>	DLL Version 2.004	Page 76/91

#### 3.15. How to Run Calibration functions for 5 devices

### 3.15.1. We have 5 devices

The device ID's are in the:
arrayID(5) = {sModuleID1, sModuleID2, sModuleID3, sModuleID4, sModuleID5}

## 3.15.2. Offset Calculation only

1) Start Offset Calculation for 5 devices.

```
1.1) Repeat F28_StartAutoCalOffsetOnly for each unit,
For Id = 0 to 4,
    F28_StartAutoCalOffsetOnly(arrayID[i], m_wNbCycles, m_wInterCycle);
Next.
```

2) Wait EOC of Offset for 5 devices.

Do:

- 2.1) Read Real time for each unit,
   F28 GetRealTimeData(arrayID[i], m realTime)
- 2.2) Display "Real time" for each unit,
- 2.3) If End of cycle, read last result,

F28\_GetLastResult(arrayID[i], m\_Result)

- 2.4) Display last result,
- 2.5) If Number of cycles is not reached, start group (start next cycle for all unit),

```
F28_StartCycleByGroup(ucGroup)
Or,
For Id = 0 to 4,
    F28_StartCycle(arrayID[i])
Next,
Or,
```

Wait till intercycle elapsed,

While (not F28\_GetEOCOffset(arrayID[i]))

3) Read Auto-calibration alarm for the 5 units, at the end of calibration,

```
For Id = 0 to 4
Read alarm code
```

F28\_GetAutoCalAlarm(arrayID[i])

If no Alarm read and save parameters,

F28\_GetParameters(arrayID[i], &tPara)

Save parameters

Next

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 2115	DLL Version 2.004	Page 77/91

#### 3.15.3. Volume & Offset Calculation

1) Start Offset calculation 1.1) Repeat F28\_StartAutoCalOffsetOnly for each unit For Id = 0 to 4 F28\_StartAutoCalOffsetOnly(arrayID[i], m\_wNbCycles, m\_wInterCycle); Next 2) Wait EOC of Offset for 5 devices, 2.1) Read Real time for each unit, F28\_GetRealTimeData(arrayID[i], m\_realTime) 2.2) Correction leak to Pa/s, m realTime.fLeakValue = m realTime.fLeakValue \* 1000 m\_realTime.ucUnitLeak = F28\_LEAK\_UNITS.LEAK\_PASEC **2.3)** Display Real time for each unit, 2.4) If end of cycle, last result, F28 GetLastResult(arrayID[i], m Result) 2.5) Correction leak to Pa/s m\_Result.fLeakValue = m\_Result.fLeakValue \* 1000 m Result.ucUnitLeak = F28 LEAK UNITS.LEAK PASEC 2.6) Display Last Result, 2.7) If Number of Cycles is not reached, start group (start next cycle for all units), F28\_StartCycleByGroup(ucGroup) Or, For Id = 0 to 4, F28\_StartCycle(arrayID[i]) Next. Or, Wait till intercycle elapsed,

- 3) Select/Plug master leak for all devices.
- 4) Start volume Calculation for all devices,
  - 1.1 Repeat F28\_StartAutoCalVolume for each unit

While (not F28\_GetEOCOffset(arrayID[i]))

```
For Id = 0 to 4
```

```
F28_StartAutoCalVolume(arrayID[i], m_wNbCycles, m_wInterCycle, m_fVolumeLeak, m_fVolumePressure, m_fVolumeMin, m_fVolumeMax)
```

Next

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 21115	DLL Version 2.004	Page 78/91

5) Wait EOC of Volume Calibration for 5 devices

Do:

**5.1)** Read Real time for each unit,

```
F28_GetRealTimeData(arrayID[i], m_realTime)
```

5.2) Correction leak to Pa/s,

```
m_realTime.fLeakValue = m_realTime.fLeakValue * 1000
m_realTime.ucUnitLeak = F28_LEAK_UNITS.LEAK_PASEC
```

- 5.3) Display Real time for each unit,
- 5.4) If end of cycle, Read last result,

```
F28_GetLastResult(arrayID[i], m_Result)
```

5.5) Correction leak to Pa/s,

```
m_Result.fLeakValue = m_Result.fLeakValue * 1000
m_Result.ucUnitLeak = F28_LEAK_UNITS.LEAK_PASEC
```

- 5.6 Display last result,
- 5.7 If Number Of Cycles Not Reached, Start next cycle for all unit,

```
- F28_StartCycleByGroup(ucGroup)
```

Or,

For Id = 0 to 4,

F28\_StartCycle(arrayID[i])

Next.

Or,

Wait till intercycle elapsed

While (not F28\_GetEOCVolume(arrayID[i]))

6) Read Auto-calibration alarm for the 5 units, at the end of calibration,

```
For Id = 0 to 4,
```

Read alarm code,

F28\_GetAutoCalAlarm(arrayID[i])

If no alarm, read and save parameters,

F28\_GetParameters(arrayID[i], &tPara)

Save parameters,

Next.

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
.   2111 %	DLL Version 2.004	Page 79/91


### 4. APPENDICIES 1

### 4.1. WHAT'S NEEDED FOR USING THE SAMPLES PROJECT C++/MFC / C# / VB.NET

- ➤ Microsoft Visual Studio 2013 Update5 must be installed,
- Microsoft.Net Framework 4.5,
- DLL Ethernet interface: F28LightControl\_ETH.dll.


### 4.2. VISUAL C++/MFC SAMPLE


# 4.2.1. Build Project





Release → for Release,

### Debug $\rightarrow$ for debug.










BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
	DLL Version 2.004	Page 81/91


#### 4.3. VISUAL C# SAMPLE


# 4.3.1. Build Project





### Release → for Release,

## Debug $\rightarrow$ for debug.










BEL	Programmers' manual	IDENTIFICATION
<b>ATEQ</b>	F28Light Control	
•  <del>2115</del>	DLL Version 2.004	Page 83/91


### 4.4. VISUAL BASIC .NET SAMPLE


# 4.4.1. Build Project





Release → for Release,

# Debug $\rightarrow$ for debug.









BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
- <del> </del>	DLL Version 2.004	Page 85/91

#### 4.5. SAMPLE CODE IN VB.NET

## 4.5.1. Get & Display Ethernet information

```
' Convert from IP string to Long
Private Function IPString2Long(ByVal DottedIP As String) As Long
       Dim arrDec() As String
       Dim lResult As Long
       lResult = 0
       If DottedIP <> "" Then
              arrDec = DottedIP.Split(".")
              If (arrDec.Length = 4) Then
                     lResult = CLng(arrDec(3)) * 2 ^ 24 + CLng(arrDec(2)) * 2 ^ 16 +
                     CLng(arrDec(1)) * 2 ^ 8 + CLng(arrDec(0))
              End If
       End If
       Return lResult
End Function
' Read & display Ethernet information
Private Function GetEthernetInformation(ByVal sModuleID As Short, ByRef Info As T_ETH_INFO) As
Short
       Dim sRet As Short
       Dim strBuff As String
       Dim ulIP As ULong
       Dim strMsg As String
       Const ucMaxBuff As Byte = 30
       strMsg = " ....."
       DisplayTxt(strMsg)
       ' Read soft version
       If (sRet = F28_RETURN.F28 OK) Then
              strBuff = Space(ucMaxBuff)
              sRet = F28_GetETHSoftVersion(sModuleID, strBuff, ucMaxBuff - 1)
              If (sRet = F28_RETURN.F28_OK) Then
                     Info.strVersion = strBuff
                     strMsg = " . Ethernet soft version : " + Info.strVersion
                     DisplayTxt(strMsg)
              End If
       End If
       ' Read hard version
       If (sRet = F28_RETURN.F28_OK) Then
              strBuff = Space(ucMaxBuff)
              sRet = F28_GetETHHardVersion(sModuleID, strBuff, ucMaxBuff - 1)
              If (sRet = F28_RETURN.F28_OK) Then
                     Info.strHardVersion = strBuff
                     strMsg = " . Ethernet hard version : " + Info.strHardVersion
                     DisplayTxt(strMsg)
              End If
       End If
```

BEL	Programmers' manual	IDENTIFICATION
<b>ATEQ</b>	F28Light Control	
.   2111 5	DLL Version 2.004	Page 86/91

```
' Read IP address
sRet = F28_GetAddressIP(sModuleID, ulIP)
If (sRet = F28_RETURN.F28_OK) Then
       Dim curIPAdd As New IPAddress(ulIP)
       Info.strIP = curIPAdd.ToString()
       strMsg = " . Ethernet IP address : " + Info.strIP
       DisplayTxt(strMsg)
End If
' Read Mask
If (sRet = F28 RETURN.F28 OK) Then
       sRet = F28 GetSubnetMask(sModuleID, ulIP)
       If (sRet = F28_RETURN.F28_OK) Then
              Dim curIPAdd As New IPAddress(ulIP)
              Info.strSubnetMask = curIPAdd.ToString()
              strMsg = " . Ethernet Subnet mask : " + Info.strSubnetMask
              DisplayTxt(strMsg)
       End If
End If
' Read gateway
If (sRet = F28_RETURN.F28_OK) Then
       sRet = F28 GetGatewayAddressIP(sModuleID, ulIP)
       If (sRet = F28_RETURN.F28_OK) Then
              Dim curIPAdd As New IPAddress(ulIP)
              Info.strGateway = curIPAdd.ToString()
              strMsg = " . Ethernet Gateway : " + Info.strGateway
              DisplayTxt(strMsg)
       End If
End If
' Read MAC address
If (sRet = F28 RETURN.F28 OK) Then
       strBuff = Space(ucMaxBuff)
       sRet = F28_GetMACAddress(sModuleID, strBuff, ucMaxBuff - 1)
       If (sRet = F28 RETURN.F28 OK) Then
              Info.strMACAddress = strBuff
              strMsg = " . Ethernet MAC addr : " + Info.strMACAddress
              DisplayTxt(strMsg)
       End If
End If
strMsg = " ....."
DisplayTxt(strMsg)
Return sRet
```

**End Function** 

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
-  <del></del>	DLL Version 2.004	Page 87/91

#### 4.5.2. Get module information

```
' GetModuleInfo
Private Function GetModuleInfo(ByVal sModuleID) As Short
      Dim sRetCode As Short
      Dim strBuff As String
      Dim strMsg As String
      sRetCode = F28_RefreshModuleInformations(sModuleID)
      If (sRetCode = F28_RETURN.F28_OK) Then
             strBuff = Space(100)
             sRetCode = F28_GetSerialNumber(sModuleID, strBuff, 20)
             If (sRetCode = F28_RETURN.F28_OK) Then
             strMsg = strBuff.Insert(0, " . Serial number : ")
             DisplayTxt(strMsg)
             End If
      End If
      If (sRetCode = F28LightControl.F28 RETURN.F28 OK) Then
             strBuff = Space(100)
             sRetCode = F28 GetModuleHardVersion(sModuleID, strBuff, 20)
             If (sRetCode = F28LightControl.F28_RETURN.F28_OK) Then
                   strMsg = strBuff.Insert(0, " . Module harware version : ")
                   DisplayTxt(strMsg)
             End If
      End If
      If (sRetCode = F28LightControl.F28_RETURN.F28_OK) Then
             strBuff = Space(100)
             sRetCode = F28 GetModuleSoftVersion(sModuleID, strBuff, 20)
             If (sRetCode = F28LightControl.F28 RETURN.F28 OK) Then
                   strMsg = strBuff.Insert(0, " . Module software version : ")
                   DisplayTxt(strMsg)
             End If
      End If
      ' 1.301 Get Ethernet info
      If (sRetCode = F28 RETURN.F28 OK) Then
             sRetCode = GetEthernetInformation(sModuleID, m_deviceEthernetInfo)
      End If
      GetModuleInfo = sRetCode
```

**End Function** 

BEL	Programmers' manual	IDENTIFICATION
_ATEQ	F28Light Control	
	DLL Version 2.004	Page 88/91

## 4.5.3. Read real time status & Read Result cycle

```
' Read & display real time status & Measurement
Private Sub m_TimerRealTime_Tick(sender As Object, e As EventArgs) Handles
m_TimerRealTime.Tick
      Dim sRetCode As Short
      Dim wCount As UShort
      If m_bAPIOpened And F28_IsModuleConnected(m_sModuleID) Then
             ' Read real time status & measurement
             sRetCode = F28_GetRealTimeData(m_sModuleID, m_realTime)
             If sRetCode = F28_RETURN.F28_OK Then
                   ' Display real time
                   DisplayRealTime()
                   ' If end of cycle -> Read last result & display
                   If (m_realTime.ucEndCycle > 0) Then
                          ' Stop real time reading at EOC
                          m_TimerRealTime.Stop()
                          ' Read Last Result
                          sRetCode = F28_GetLastResult(m_sModuleID, m_Result)
                          If sRetCode = F28 RETURN.F28 OK Then
                                DisplayResult(0)
                          End If
                          ' Read Get fifo Result count
                          wCount = F28 GetResultsCount(m sModuleID)
                          m_labelFifoCount.Text = wCount.ToString
                          ' Read fifo if demands
                          If wCount > 0 And m_chkReadFifo.Checked Then
                                 ' Read fifo
                                sRetCode = F28 GetNextResult(m sModuleID, m Result)
                                If sRetCode = F28_RETURN.F28_OK Then
                                       DisplayResult(1)
                                End If
                                wCount = F28_GetResultsCount(m_sModuleID)
                                m_labelFifoCount.Text = wCount.ToString
                          End If
                   End If
            End If
      End If
' Read & display counter
If sRetCode = F28 RETURN.F28 OK Then
      sRetCode = F28_GetCommunicationStatistics(m_sModuleID, m_rCptComm)
      If sRetCode = F28_RETURN.F28_OK Then
             DisplayCounter()
      End If
End If
End Sub
```


BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
	DLL Version 2.004	Page 89/91

# 4.5.4. Auto zero pressure

```
' Auto Zero pressure
Private Sub btnAZPressure_Click(sender As Object, e As EventArgs) Handles
btnAZPressure.Click
      Dim fDumpTime As Single
      Dim sRetCode As Short
      If m_bAPIOpened And F28_IsModuleConnected(m_sModuleID) Then
             ' Get dump time in sec
             fDumpTime = Convert.ToSingle(textBoxAZDumpTime.Text)
             sRetCode = F28_StartAutoZeroPressure(m_sModuleID, fDumpTime)
             If (sRetCode = F28_RETURN.F28_OK) Then
                   DisplayTxt("Start auto zero Ok !!!")
             Else
                   DisplayTxt("Start auto zero error !!!")
             End If
      End If
End Sub
```

BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
. 2113	DLL Version 2.004	Page 90/91

## 4.6. START AUTO CAL OFFSET FOR MORE THAN ONE HEAD IN VB.NET



BEL	Programmers' manual	IDENTIFICATION
ATEQ	F28Light Control	
	DLL Version 2.004	Page 91/91

Below is a example of VB.net code, how to do a Start /Start Auto Cal Offset only for more than one heads.

We need only to repeat the command to each heads.

```
______
    ' Start auto cal offset for all heads inside the listBox
Private Sub Button5_Click(sender As Object, e As EventArgs) Handles btnOffset2.Click
Dim n As Integer
      Dim strBuff As String
      Dim sNum As Short
      Dim sRet As Short
      Dim wNbCycles As UShort
      Dim wInterCycle As UShort
      Dim fOffsetMax As Single
      wNbCycles = Convert.ToInt16(textBoxCycleNumber.Text)
      wInterCycle = Convert.ToInt16(textBoxIntercycle.Text)
      fOffsetMax = Convert.ToSingle(textBoxOffset.Text)
      ' Get number of heads inside the listbox
      n = m_listBox2Heads.Items.Count
      ' If not empty
      If n > 0 Then
' Repeat for all heads
      For i = 0 To n - 1
            ' Get sModuleID for head i
            strBuff = m listBox2Heads.Items.Item(i)
            sNum = CShort(strBuff)
            ' Check if the module is connected
            If m_bAPIOpened And F28_IsModuleConnected(sNum) Then
                   ' Start auto Cal Offset for head i
                  sRet = F28_StartAutoCalOffsetOnly(sNum, wNbCycles, wInterCycle,
                  fOffsetMax)
                  If (sRet = F28 RETURN.F28 OK) Then
                         DisplayTxt("Start Offset Ok -> " + sNum.ToString())
                  Else
                         DisplayTxt("Start Offset error -> " + sNum.ToString())
                  End If
            End If
            Next
      End If
```

End Sub